



PC-MILER[®]
AS400 **30**

User Guide



www.pcmiler.com
pcmiler.com/support



ALL RIGHTS RESERVED

You may print one (1) copy of this document for your personal use. Otherwise, no part of this document may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language, in any form or by any means electronic, mechanical, magnetic, optical, or otherwise, without prior written permission from ALK Technologies, Inc.

Microsoft and Windows are registered trademarks of Microsoft Corporation in the United States and other countries.

IBM is a registered trademark of International Business Machines Corporation.

*PC*MILER®, CoPilot® Truck™, ALK®, RouteSync®, and TripDirect® are registered trademarks of ALK Technologies, Inc.*

Truck Stop location data © Copyright 2016 Comdata Inc, 5301 Maryland Way, Brentwood, TN 37027. All Rights Reserved.

Traffic information provided by INRIX © 2016. All Rights Reserved by INRIX, Inc.

*SPLC data used in PC*MILER products is owned, maintained and copyrighted by the National Motor Freight Traffic Association, Inc.*

Canadian Postal Codes data based on Computer File(s) licensed from Statistics Canada. © Copyright, HER MAJESTY THE QUEEN IN RIGHT OF CANADA, as represented by the Minister of Industry, Statistics Canada 2003-2016. This does not constitute an endorsement by Statistics Canada of this product.

Contains information licensed under the Open Government License – Canada.

<http://open.canada.ca/en/open-government-licence-canada>

Xceed Software – The Software is Copyright © 1994-2016 Xceed Software Inc., All Rights Reserved. The Software is protected by Canadian and United States copyright laws, international treaties and other applicable national or international laws.

United Kingdom full postal code data supplied by Ordnance Survey Data © Crown copyright and database right 2016. OS OpenData™ is covered by either Crown Copyright, Crown Database copyright, or has been licensed to the Crown.

Certain Points of Interest (POI) data by Infogroup © Copyright 2016. All Rights Reserved.

Geographic feature POI data compiled by the U.S. Geological Survey.

Oil and Gas field content provided by GeoTrac Systems Inc. © Copyright 2016. All Rights Reserved.

Cartographic data provided by multiple sources including Instituto Nacional de Estadística y Geografía, U.S. Geological Survey, Natural Earth and © Department of Natural Resources Canada. All Rights Reserved.

Copyright HERE Data © 2016 – All Rights Reserved. HERE Data © is subject to the terms set forth at http://corporate.navteq.com/supplier_terms.html.

Source of map data for Mexico provided by Instituto Nacional de Estadística y Geografía.

All Retail Prices for Pilot Flying J locations are subject to change and are subject to Pilot Flying J's disclaimer set forth at <http://www.pilotflyingj.com/disclaimer>.

National Elevation Data produced by the U.S. Geological Survey.

Satellite Imagery © Digital Globe, Inc. All Rights Reserved.

Weather data provided by Environment Canada (EC), U.S. National Weather Services (NWS), U.S. National Oceanic and Atmospheric Administration (NOAA), and AerisWeather. © Copyright 2016. All Rights Reserved.

Copyright SanGIS 2009 – All Rights Reserved.

Data provided by permission of King County, Washington.

ALK Data © 2016 – All Rights Reserved.

ALK Technologies, Inc. reserves the right to make changes or improvements to its programs and documentation materials at any time and without prior notice.

Table of Contents

PC*MILER® Product Line End User License Agreement	i
PC*MILER-AS400 Version Notes – Please Read	1
1.0 Introduction	2
2.0 Hardware and Software Requirements	3
2.1 System Requirements	3
2.2 Accessing User’s Guides for PC*MILER Products	5
3.0 Installation	6
3.1 Installation Overview	7
3.2 AS400 Side Installation	7
3.3 PC Side Installation	11
3.4 Creation of Desktop Icons	21
4.0 Starting and Stopping the Mileage Server	23
4.1 Starting the Mileage Server	23
4.2 Stopping the Interface	24
4.3 Configuring the Use of Mexican Postal Codes	25
5.0 Using PC*MILER for the AS400	26
5.1 Function Keys	31
5.2 Basic Mileage, Cost and Time Report	32
5.3 State Mileage Report	34
5.4 Detailed Driving Directions Report.....	37
6.0 Using PC*MILER with other Transportation Software	39
6.1 Technical Overview	43
6.2 Request and Response Field Parameters	45
6.2.1 Stop Validation (VA) Request and Response.....	46
6.2.2 Point-to-point Miles (MI) Request and Response	48
6.2.3 State Miles (SM) Request and Response	51
6.2.4 Detailed Route Information (HS) Request and Response	54
6.2.5 Upgrade Notice	57
6.2.6 City/Address to Lat/Long Coordinates (LL) Request and Response.....	57
6.3 Sample Request and Response Records.....	59
7.0 Using PC*MILER Tolls with Other Transportation Software	60
7.1 Technical Overview	64

7.2 Request and Response Field Parameters	66
7.2.1 Stop Validation (VA) Request and Response.....	67
7.2.2 Point-to-point Miles (MI) Request and Response	69
7.2.3 State Miles (SM) Request and Response	72
7.2.4 Detailed Route Information (HS) Request and Response	76
7.2.5 Upgrade Notice	80
7.2.6 City/Address to Lat/Long (LL) Request and Response	81
7.2.7 Optional: PC Server Version (VN) Request and Response.....	82
7.2.8 Sample Request and Response Records	83
8.0 Menus	84
9.0 Common Questions and Installation Problems	86
10.0 Technical Support.....	88
11.0 About ALK® Technologies	89
Appendix A: Backward Compatibility	90
Appendix B: Configuring an N/S Router For Use With PC*MILER-AS400 ..	91
Appendix C: Configuring AnyNet On the AS400.....	95
Appendix D: Configuring Client Access Express To Work With PC*MILER-AS400	96
Appendix E: The Sleep Feature For PC Connection/ IPL Issues	101
Appendix F: PCMSERVE.INI Settings	103
Appendix G: AS400.LOG Error Codes	106
Appendix H: Technical Implications of PC*MILER Tolls	108
Appendix I: Renamed Program Objects	113
Appendix J: Setting Toll Discount Program Membership.....	115
Appendix K: Setting the Default Cost Per Mile or Kilometer.....	116
Appendix L: Running PC*MILER and PC*MILER Tolls Builds of the AS400 Interface on the Same PC	117

PC*MILER® Product Line END-USER LICENSE AGREEMENT

1. **Grant of License:** Subject to the terms, conditions, use limitations and payment of fees as set forth herein, ALK Technologies, Inc. ("ALK") grants the end-user ("you") a non-assignable, non-transferable, non-exclusive license to install and use the PC*MILER solution(s) (including traffic data and fuel subscriptions) you have purchased ("PC*MILER") on a single personal computer. The PC*MILER software, data and documentation are provided for your personal, internal use only and not for resale. They are protected by copyright held by ALK and its licensors and are subject to the following terms and conditions which are agreed to by you, on the one hand, and ALK and its licensors (including their licensors and suppliers) on the other hand.
2. **Title:** You acknowledge that the PC*MILER computer programs, data, concepts, graphics, documentation, manuals and other material owned by, developed by or licensed to ALK, including but not limited to program output (together, "program materials"), are the exclusive property of ALK or its licensors. You do not secure title to any PC*MILER program materials by virtue of this license.
3. **Copies:** You may make one (1) copy of the PC*MILER program materials, provided you retain such copy in your possession and use it solely for backup purposes. You agree to reproduce the copyright and other proprietary rights notices of ALK and its licensors on such a copy. Otherwise, you agree not to copy, reverse engineer, interrogate, or decode any PC*MILER program materials or attempt to defeat protection provided by ALK for preventing unauthorized copying or use of PC*MILER or to derive any source code or algorithms therefrom. You acknowledge that unauthorized use or reproduction of copies of any program materials or unauthorized transfer of any copy of the program materials is a serious crime and is grounds for suit for damages, injunctive relief and attorneys' fees.
4. **Limitations on Transfer:** This license is granted to you by ALK. You may not directly or indirectly lease, sublicense, sell, disseminate, or otherwise transfer PC*MILER or any PC*MILER program materials to third parties, or offer information services to third parties utilizing the PC*MILER program materials without ALK's prior written consent. To comply with this limitation, you must uninstall and deactivate PC*MILER from your computer prior to selling or transferring that computer to a third party.
5. **Limitations on Network Access:** You may not allow end-users or software applications on other computers or devices to directly or indirectly access this copy of PC*MILER via any type of computer or communications network (including but not limited to local area networks, wide area networks, intranets, extranets, the internet, virtual private networks, Wi-Fi, Bluetooth, and cellular and satellite communications

systems), using middleware (including but not limited to Citrix MetaFrame and Microsoft Terminal Server) or otherwise (including but not limited to access through PC*MILER interface products), or install or use PC*MILER on a network file server, without first notifying ALK, executing a written supplemental license agreement, and paying the license fee that corresponds to the number and types of uses to which access is to be allowed.

6. Limitations on Data Extraction: You may manually extract data (including but not limited to program output such as distances, maps, and driving directions) from PC*MILER and use it in other applications on the same computer on which PC*MILER is legally licensed and installed, as permitted below. You may not transfer data extracted from PC*MILER onto any other computer or device unless you have licensed PC*MILER for that computer or device. You agree that you will not, nor will you permit your trade partners or anyone else to, use content derived from PC*MILER, including route line data, nor display such data or integrate such data into another provider's service, including, but not limited to, Google or Bing. You agree not to pre-fetch, retrieve, cache, index, or store any data, content, or other portion of the product output at any time, provided, however, that you may temporarily store (for less than thirty (30) days) limited amounts of such content for the sole and exclusive purpose of enhancing the performance of your implementation due to network latency, and only if you do so securely and in a manner that: (a) does not permit use of the content outside of the scope of this Agreement; (b) does not manipulate or aggregate any content or portion thereof; (c) does not prevent ALK from accurately tracking usage; and (d) does not modify attribution of the product in any way.
7. Limitations on Mobile Communications: Without limiting the generality of the foregoing, you may not transmit PC*MILER street-level driving directions through mobile communications systems such as satellite, or cellular services or to mobile devices such as computers, telematics systems, on board or mobile computers or Smartphones, handhelds, pagers, electronic recording devices or telephones without first executing a written supplemental license agreement with ALK and paying the license fee that corresponds to the number and types of devices and systems to and through which transmission is to be permitted.
8. Limitations on Disclosure: You may disclose PC*MILER distances to trading partners, in the course of their providing services to you, for specific origin-destination moves for which you provide transportation services and use PC*MILER distances as a basis for payment. You may not make any other disclosure of PC*MILER programs and materials, including, but not limited to, program output, to anyone outside the legal entity that paid for and holds this license, without prior written permission of ALK. You acknowledge that the PC*MILER programs and materials, developed by or licensed to ALK are very valuable to ALK and its licensors, and their use or disclosure to third parties, except as permitted by this license or by a written supplemental license agreement with ALK, is strictly prohibited.

9. Security: You agree to take reasonable and prudent steps to safeguard the security of the PC*MILER program materials and to notify ALK immediately if you become aware of the theft or unauthorized possession, use, transfer or sale of the PC*MILER program materials licensed to you by ALK.
10. Acceptance: You are deemed to have accepted the PC*MILER program materials upon receipt.
11. Warranties: ALK represents and warrants that:
 - a) For ninety (90) days from date of purchase, PC*MILER, when delivered and properly installed, will function substantially according to its specifications on a computer purchased independently by you.
 - b) For ninety (90) days from date of purchase, the software media on which ALK provides PC*MILER to you will function substantially free of errors and defects. ALK will replace defective media during the warranty period at no charge to you unless the defect is the result of accident, abuse, or misapplication of the product.
 - c) THE FOREGOING WARRANTIES ARE IN LIEU OF ALL OTHER WARRANTIES EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITING THE GENERALITY OF THE FOREGOING ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR USE. THE PC*MILER PROGRAM, DATA AND DOCUMENTATION IS SOLD "AS IS". IN NO EVENT SHALL ALK OR ITS LICENSORS BE LIABLE FOR ANY INDIRECT, SPECIAL OR CONSEQUENTIAL DAMAGES SUCH AS, BUT NOT LIMITED TO, LOSS IN CONNECTION WITH OR ARISING OUT OF THE EXISTENCE OF THE FURNISHING, FUNCTIONING OR USE OF ANY ITEM OF SOFTWARE, DATA OR SERVICES PROVIDED FOR IN THIS AGREEMENT. IN NO EVENT SHALL DAMAGES TO WHICH ALK MAY BE SUBJECT UNDER THIS AGREEMENT EXCEED THE CONTRACT PRICE. THIS WARRANTY SHALL NOT ACCRUE TO THE BENEFIT OF THIRD PARTIES OR ASSIGNEES.
12. Disclaimer: The data may contain inaccurate, incomplete or untimely information due to the passage of time, changing circumstances, sources used and the nature of collecting comprehensive geographic data, any of which may lead to incorrect results. PC*MILER's suggested routings, fuel and traffic data are provided without a warranty of any kind. The user assumes full responsibility for any delay, expense, loss or damage that may occur as a result of their use. The user shall have no recourse against Canada, whether by way of any suit or action, for any loss, liability, damage or cost that may occur at any time, by reason of possession or use of Natural Resources Canada data.
13. Termination: This Agreement will terminate immediately upon any of the following events:

- a) If you seek an order for relief under the bankruptcy laws of the United States or similar laws of any other jurisdiction, or a composition with or assignment for the benefit of creditors, or dissolution or liquidation, or if proceedings under any bankruptcy or insolvency law are commenced against you and are not discharged within thirty (30) calendar days.
- b) If you materially breach any terms, conditions, use limitations, payment obligations, or any other terms of this Agreement.
- c) Upon expiration of any written supplemental license agreement between you and ALK of which this license is a part.
14. Obligations on Termination: Termination or expiration of this Agreement shall not be construed to release you from any obligations that existed prior to the date of such termination or expiration.
15. Hold Harmless and Indemnity: To the maximum extent permitted by applicable law, you agree to hold harmless and indemnify ALK and its parent company, subsidiaries, affiliates, officers, agents, licensors, owners, co-branders, other partners, and employees from and against any third party claim (other than a third party claim for Intellectual Property Rights) arising from or in any way related to your use of PC*MILER, including any liability or expense arising from all claims, losses, damages (actual and/or consequential), suits, judgments, litigation costs and attorneys' fees, of every kind and nature. ALK shall use good faith efforts to provide you with written notice of such claim, suit or action.
16. Disclosure for Products Containing Certain Data:
- a) Historical or Real-time Traffic data: traffic data, including historical traffic data, is licensed as an optional subscription service which must be renewed annually for continued use. ALK and its licensor(s) will use commercially reasonable efforts to make traffic data available at least 99.5% of the time each calendar month, excluding minor performance or technical issues as well as downtime attributable to necessary maintenance, and Force Majeure.
- b) Fuel data: fuel data is licensed as an optional a subscription service which must be renewed annually for continued use.

This data is provided to you "as is," and you agree to use it at your own risk. ALK and its licensors (and their licensors and suppliers) make no guarantees, representations or warranties of any kind, express or implied, arising by law or otherwise, including but not limited to, content, quality, accuracy, completeness, effectiveness, reliability, fitness for a particular purpose, usefulness, use or results to be obtained from this Data, or that the Data or server will be uninterrupted or error-free.

17. Limitations on Export: You hereby expressly agree not to export PC*MILER, in whole or in part, or any data derived therefrom, in violation of any export or other laws or regulations of the United States.
18. Aggregated Data: ALK may, from time to time, share information about You with parent and sister or affiliated companies for business purposes and when necessary for it to perform work under this Agreement. In addition, ALK may, and is hereby authorized to, use, share and provide certain aggregated, non-identifiable information derived from Your use of PC*MILER to third parties.
19. ALK Cloud Feature: ALK Cloud feature will store in anonymized way Your data in a cloud account in order to allow You to securely synchronize Your data with other users in Your organization. End-user data is deemed the confidential information of end-user. For more information you may refer to ALK's Privacy Policy.
20. Additional Use Terms, Conditions, Restrictions and Obligations: This agreement and your use of PC*MILER is expressly subject to the ALK Privacy Policy and the Navteq (HERE) and ALK End User License Agreement Terms and Conditions respectively ("Navteq EULA") and ("ALK EULA") set forth below. YOU ACKNOWLEDGE AND AGREE THAT YOU MAY NOT USE PC*MILER IF YOU DO NOT ACCEPT THE TERMS AND CONDITIONS OF BOTH THE NAVTEQ AND ALK EULA AND THAT YOU ACKNOWLEDGE THAT YOU HAVE REVIEWED AND ACCEPT THE TERMS AND CONDITIONS OF BOTH THE NAVTEQ AND ALK EULA BY INSTALLING OR ACTUALLY USING PC*MILER.
21. Miscellaneous: This agreement shall be construed and applied in accordance with the laws of the State of New Jersey. The Courts of the State of New Jersey shall be the exclusive forum for all actions or interpretation pertaining to this agreement. Any amendments or addenda to this agreement shall be in writing executed by all parties hereto. This is the entire agreement between the parties and supersedes any prior or contemporaneous agreements or understandings. Should any provision of this agreement be found to be illegal or unenforceable, then only so much of this agreement as shall be illegal or unenforceable shall be stricken and the balance of this agreement shall remain in full force and effect.
22. Date: This EULA was last updated on June 4, 2016. Visit www.pcmiler.com for regular updates.

END USER LICENSE AGREEMENT FOR NAVTEQ (HERE) DATA

This licence applies to NAVTEQ data included in your Software, if any, as well as to NAVTEQ data you obtain separately that is formatted for use with your Software.

The data ("**Data**") is provided for your personal, internal use only and not for resale. It is protected by copyright, and is subject to the following terms and conditions which are

agreed to by you, on the one hand, and ALK Technologies Inc. (“**ALK**”) and its licensors (including their licensors and suppliers) on the other hand.

© 2016 NAVTEQ. All rights reserved.

Personal Use Only. You agree to use this Data together with PC*MILER for the solely personal, non-commercial purposes for which you were licensed, and not for service bureau, time-sharing or other similar purposes. Accordingly, but subject to the restrictions set forth in the following paragraphs, you may copy this Data only as necessary for your personal use to (i) view it, and (ii) save it, provided that you do not remove any copyright notices that appear and do not modify the Data in any way. You agree not to otherwise reproduce, copy, modify, decompile, disassemble or reverse engineer any portion of this Data, and may not transfer or distribute it in any form, for any purpose, except to the extent permitted by mandatory laws. Multi-disc sets may only be transferred or sold as a complete set as provided by ALK and not as a subset thereof.

Restrictions. Except where you have been specifically licensed to do so by ALK, and without limiting the preceding paragraph, you may not (a) use this Data with any products, systems, or applications installed or otherwise connected to or in communication with vehicles, capable of vehicle navigation, positioning, dispatch, real time route guidance, fleet management or similar applications; or (b) with or in communication with any positioning devices or any mobile or wireless-connected electronic or computer devices, including without limitation cellular phones, palmtop and handheld computers, pagers, and personal digital assistants or PDAs.

Warning. The Data may contain inaccurate or incomplete information due to the passage of time, changing circumstances, sources used and the nature of collecting comprehensive geographic data, any of which may lead to incorrect results.

No Warranty. This Data is provided to you “as is,” and you agree to use it at your own risk. ALK and its licensors (and their licensors and suppliers) make no guarantees, representations or warranties of any kind, express or implied, arising by law or otherwise, including but not limited to, content, quality, accuracy, completeness, effectiveness, reliability, fitness for a particular purpose, usefulness, use or results to be obtained from this Data, or that the Data or server will be uninterrupted or error-free.

Disclaimer of Warranty. ALK AND ITS LICENSORS (INCLUDING THEIR LICENSORS AND SUPPLIERS) DISCLAIM ANY WARRANTIES, EXPRESS OR IMPLIED, OF QUALITY, PERFORMANCE, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT. Some States, Territories and Countries do not allow certain warranty exclusions, so to that extent the above exclusion may not apply to you.

Disclaimer of Liability. ALK AND ITS LICENSORS (INCLUDING THEIR LICENSORS AND SUPPLIERS) SHALL NOT BE LIABLE TO YOU: IN RESPECT OF ANY CLAIM,

DEMAND OR ACTION, IRRESPECTIVE OF THE NATURE OF THE CAUSE OF THE CLAIM, DEMAND OR ACTION ALLEGING ANY LOSS, INJURY OR DAMAGES, DIRECT OR INDIRECT, WHICH MAY RESULT FROM THE USE OR POSSESSION OF THE INFORMATION; OR FOR ANY LOSS OF PROFIT, REVENUE, CONTRACTS OR SAVINGS, OR ANY OTHER DIRECT, INDIRECT, INCIDENTAL, SPECIAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF YOUR USE OF OR INABILITY TO USE THIS INFORMATION, ANY DEFECT IN THE INFORMATION, OR THE BREACH OF THESE TERMS OR CONDITIONS, WHETHER IN AN ACTION IN CONTRACT OR TORT OR BASED ON A WARRANTY, EVEN IF ALK OR ITS LICENSORS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Some States, Territories and Countries do not allow certain liability exclusions or damages limitations, so to that extent the above may not apply to you.

Export Control. You agree not to export from anywhere any part of the Data provided to you or any direct product thereof except in compliance with, and with all licenses and approvals required under, applicable export laws, rules and regulations.

Entire Agreement. These terms and conditions constitute the entire agreement between ALK (and its licensors, including their licensors and suppliers) and you pertaining to the subject matter hereof, and supersedes in their entirety any and all written or oral agreements previously existing between us with respect to such subject matter.

Governing Law. The above terms and conditions shall be governed by the laws of Illinois, without giving effect to (i) its conflict of laws provisions, or (ii) the United Nations Convention for Contracts for the International Sale of Goods, which is explicitly excluded. You agree to submit to the jurisdiction of the Illinois for any and all disputes, claims and actions arising from or in connection with the Data provided to you hereunder.

Government End Users: If the Data is being acquired by or on behalf of the United States Government or any other entity seeking or applying rights similar to those customarily claimed by the United States government, the Data is a "commercial item" as that term is defined at 48 C.F.R ("FAR") 2.101, is licensed in accordance with End-User Terms and each copy of Data delivered or otherwise furnished shall be marked and embedded as appropriate with the following "Notice of Use" and shall be treated in accordance with such Notice.

Notice of Use

Contractor (Manufacturer/Supplier) Name: NAVTEQ

Contractor (Manufacturer/Supplier) Address: 425 W. Randolph Street, Chicago, Illinois 60606

This Data is a commercial item as defined in FAR 2.101 and is subject to these End User Terms under which this Data was provided

©2016 NAVTEQ- All rights reserved

If the Contracting Officer, federal government agency, or any federal official refuses to use the legend provided herein, the Contracting Officer, federal government agency, or any federal official must notify NAVTEQ prior to seeking additional or alternative rights in the Data.

END USER LICENSE AGREEMENT FOR ALK DATA

This license applies to ALK Data included in PC*MILER if any, as well as to ALK data you obtain separately that is formatted for use with your Software.

The data (“**Data**”) is provided for your personal, internal use only and not for resale. It is protected by copyright, and is subject to the following terms and conditions which are agreed to by you, on the one hand, and ALK Technologies, Inc. (“**ALK**”) and its licensors (including their licensors and suppliers) on the other hand.

© 2016 ALK. All rights reserved.

1. Personal Use Only: “**You**” means you as an End-user or as a “Company” on behalf of its End-Users which are subject to either a Non-Disclosure Agreement as employees or a License Agreement that contains the same restrictions as herein as a Value Added Reseller. Also as used in this EULA “personal use” can also be understood in more general terms as for a Company’s use. You agree to use this Data together with PC*MILER for the solely personal, non-commercial purposes for which you were licensed, and not for service bureau, time-sharing or other similar purposes. Accordingly, but subject to the restrictions set forth in the following paragraphs, you may copy this Data only as necessary for your personal use to (i) view it, and (ii) save it, provided that you do not remove any copyright notices that appear and do not modify the Data in any way. You agree not to otherwise reproduce copy, modify, decompile, disassemble or reverse engineer any portion of this Data, and may not transfer or distribute it in any form, for any purpose, except to the extent permitted by mandatory laws.
2. Restrictions: Except where you have been specifically licensed to do so by ALK in the case of an integrated solution bundled or intended for use with specific smartphones, similar mobile communication device(s) or personal navigation device(s), and without limiting the preceding paragraph, you may not use this Data (a) with any products, systems, or applications installed or otherwise connected to or in communication with vehicles, capable of vehicle navigation, positioning, dispatch, real time route guidance, fleet management or similar applications; or (b) with or in communication with any positioning devices or any mobile or wireless-connected electronic or computer devices, including without limitation cellular phones, smartphones, palmtop and handheld computers, pagers, and personal digital assistants or PDAs.

3. Warning: The Data may contain inaccurate, untimely or incomplete information due to the passage of time, changing circumstances, sources used and the nature of collecting comprehensive geographic data, any of which may lead to incorrect results. The Data is based on official highway maps, the Code of Federal Regulations, and information provided by state governments and other licensors. It is provided without a warranty of any kind. The user assumes full responsibility for any delay, expense, loss or damage that may occur as a result of use of the Data.
4. No Warranty: This Data is provided to you "as is," and you agree to use it at your own risk. ALK and its licensors (and their licensors and suppliers) make no guarantees, representations or warranties of any kind, express or implied, arising by law or otherwise, including but not limited to, content, quality, accuracy, completeness, effectiveness, reliability, fitness for a particular purpose, usefulness, use or results to be obtained from this Data, or that the Data or server will be uninterrupted or error-free.
5. Disclaimer of Warranty: **ALK AND ITS LICENSORS (INCLUDING THEIR LICENSORS AND SUPPLIERS) DISCLAIM ANY WARRANTIES, EXPRESS OR IMPLIED, OF QUALITY, PERFORMANCE, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT.** Some States, Territories and Countries do not allow certain warranty exclusions, so to that extent the above exclusion may not apply to you.
6. Disclaimer of Liability: **ALK AND ITS LICENSORS (INCLUDING THEIR LICENSORS AND SUPPLIERS) SHALL NOT BE LIABLE TO YOU: IN RESPECT OF ANY CLAIM, DEMAND OR ACTION, IRRESPECTIVE OF THE NATURE OF THE CAUSE OF THE CLAIM, DEMAND OR ACTION ALLEGING ANY LOSS, INJURY OR DAMAGES, DIRECT OR INDIRECT, WHICH MAY RESULT FROM THE USE OR POSSESSION OF THE INFORMATION; OR FOR ANY LOSS OF PROFIT, REVENUE, CONTRACTS OR SAVINGS, OR ANY OTHER DIRECT, INDIRECT, INCIDENTAL, SPECIAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF YOUR USE OF OR INABILITY TO USE THIS INFORMATION, ANY DEFECT IN THE INFORMATION, OR THE BREACH OF THESE TERMS OR CONDITIONS, WHETHER IN AN ACTION IN CONTRACT OR TORT OR BASED ON A WARRANTY, EVEN IF ALK OR ITS LICENSORS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.** Some States, Territories and Countries do not allow certain liability exclusions or damages limitations, so to that extent the above may not apply to you.
7. Export Control! You agree not to export from anywhere any part of the Data provided to you or any direct product thereof except in compliance with and with all licenses and approvals required under, applicable export laws, rules and regulations.
8. Entire Agreement: These terms and conditions constitute the entire agreement between ALK (and its licensors, including their licensors and suppliers) and you

pertaining to the subject matter hereof, and supersedes in their entirety any and all written or oral agreements previously existing between us with respect to such subject matter.

9. Governing Law: The above terms and conditions shall be governed by the laws of the State of New Jersey. The courts of the State of New Jersey shall have exclusive jurisdiction to settle any and all disputes, claims and actions arising from or in connection with the Data provided to you hereunder. You agree to submit to such jurisdiction.

10. Canada: DISCLOSURE FOR PRODUCTS CONTAINING CANADIAN POSTAL CODE AND/OR CANADIAN STREET-LEVEL DATA: Based on Computer File(s) licensed from Statistics Canada. © Copyright, HER MAJESTY THE QUEEN IN RIGHT OF CANADA, as represented by the Minister of Industry, Statistics Canada 2003-2016. ALK Technologies, Inc. is an Authorized User of selected Statistics Canada Computer File(s) and Distributor of derived Information Products under Licensing Agreement 6147. No confidential information about an individual, family, household, organisation or business has been obtained from Statistics Canada.

=====
ALK TECHNOLOGIES, INC. | www.alk.com
=====

PC*MILER-AS400 Version Notes – Please Read

NOTE: For Version 30, the 53 Foot Trailer routing option has been replaced with the 'State + National Network' routing option to better reflect the combination in previous versions of PC*MILER's National Network and 53 Foot Trailer Networks when the 53 Foot Trailer option was selected. The interactive green screen PC*MILER program has not been updated to reflect this change. Choosing either the 53 Foot Trailer or National Network Extended Routing option will turn on the new State + National Network option.

For Third Party applications, ALK will continue to support the use of either the 'N' or '5' Network Types to turn on State + National Network Routing.

The following extended routing types will also turn on State + National Routing portion of the request:

C = National Network/Practical

D = 53 Foot Trailer/Practical

E = Toll Discouraged/National Network/Practical

F = Toll Discouraged/53 Foot Trailer/Practical

H = National Network/Shortest

I = 53 Foot Trailer/Shortest

J = Toll Discouraged/National Network/Shortest

K = Toll Discouraged/53 Foot Trailer/Shortest

There were no functional changes made in the ALKWIN or ALKTLL libraries for Version 30. If you currently have Borders Open/Closed and Use Ferry Distance Yes/No flags when you run the alkwin/pcmiler or alkttl/pcmtll commands, your ALKWIN or ALKTLL libraries are functionally up to date. The libraries that you received with the V. 30 release have two sample data structures (MISEND2 and TLSEND2) that include field mappings for the Borders Open/Closed and Use Ferry Distance flags. Updating your library is not required.

NOTE: The following features are not supported in the AS400 product line: Estimated Greenhouse Gas Emissions, RouteSync, TripDirect, Entry/Exit Toll Plaza Names in Reports, and Real-time/Historical Traffic Data.

1.0 Introduction

Congratulations! By purchasing a PC*MILER product, you have made a cost-effective investment in high quality software that is simple to learn and easy to use. PC*MILER for the AS400 uses simple-to-follow menus and requires minimal keystrokes to generate routing and mileage information. Shortest, Practical, National Network, Toll-Discouraged, and 53' Trailer routes can be calculated in a matter of seconds and can include up to 30 stops.

PC*MILER for the AS400 includes all the standard features found in the PC version, including the Hub Distance Generator, Spelling Helper, route resequencing, and user-defined time and cost estimates. You are referred to the main PC*MILER *User's Guide* for a more thorough discussion of these features. With PC*MILER-AS400, you can quickly and easily generate point-to-point miles, driving instructions, and mileage summaries broken down by toll roads and freeways

PC*MILER for the AS400 utilizes a unique distributed processing solution. This solution maximizes the efficiency of your AS400 by "farming out" repetitive mileage calculations to a PC. With PC*MILER-AS400, you can benefit from having a seamless mileage interface with your management system. Interfaces have been developed for Innovative Computing Corporation, Qualcomm, and others.

Use PC*MILER for the AS400 to audit driver logs and supplement your fuel tax reports. Increase driver productivity by using PC*MILER's driving instructions and trip sequencing. In addition, your purchase of PC*MILER-AS400 will eliminate the high costs of leasing mileage systems or paying exorbitant transaction fees.

2.0 Hardware and Software Requirements

Because PC*MILER-AS400 employs a Client server solution, the following hardware and software is required. The AS400 server uses SNA APPC data queues to communicate.

2.1 System Requirements

2.1.1 Platforms

- PC/LAN Windows® Server® (Windows Server 2012, Terminal Servers, and Server 2008 including Server 2008 R2 running in 32-bit compatibility mode for the PC*MILER user interface) and Microsoft® Windows® 7*, 8* and 10* running in 32-bit compatibility mode
 - * **For Microsoft Windows 8 and Above:** It is strongly recommended that you avoid installing to the Program Files or Program Files (x86) folder. If you need to do so, you'll have to *Run as Administrator* when you open PC*MILER.
 - * **Microsoft Windows 7 and above, and Windows Server 2012 Users:** Your license may need to be installed and activated using an Administrator Account. Once installed, you do not have to *Run as Administrator* provided you install to the recommended default directory or to another directory that doesn't require users to *Run as Administrator*. Additionally, the administrator should grant write permissions to the PC*MILER default directory since some of the newer operating systems require an administrator to grant these write permissions.
- AS/400
- CICS®/MVS
- UNIX® (AIX, HP-UX, Sun-Solaris) and Linux™
- Citrix® Metaframe and Windows Terminal Services
- TCP/IP functionality for use with other platforms

NOTE: Platforms not supported include: Windows Vista, XP, Server 2000, and Server 2003.

2.1.2 Windows Requirements

PC*MILER:

- In Version 30, automatic installation of Microsoft® .NET Framework 4.6 requires 4.5 GB, which reduces in size down to 39 MB once it is installed.
- PC*MILER – 3.1 GB hard disk space for full install, including all Add-Ons listed below and all Connectivity products.

Add-on Data Modules:

- PC*MILER|Tolls – Add 50 MB hard disk space
- PC*MILER|HazMat – Add 50 MB hard disk space
- PC*MILER|Streets (U.S. Data) – Add 1.3 GB hard disk space
- PC*MILER|Streets (Canadian Data) – Add 60 MB hard disk space
- Canadian Postal Codes – Add 50 MB hard disk space
- Standard Point Location Codes (SPLC) – Add 2 MB hard disk space

These additional components may also be installed:

- Microsoft Visual C++ 2015 Redistributable Package (x86) – 6 MB disk space
- Microsoft .Net 4.52 via NDP46-KB3045557-x86-x64-AllOS-ENU.exe – 4.5 GB

2.1.3 PC to AS400 Connectivity Options (Not Provided by ALK)

- PC with a 2+ GHz processor, 1 GB RAM recommended.
- Client Access Express V4R4MO or higher, also known as iSeries Access (recommended).
- Supports OS/400, i5/OS and IBMi operating systems; Version 4.2 (V4R2) and higher on IBM AS/400, System i and Power Systems™ hardware.

2.1.4 Other Requirements

- Internet access for license activation.
- Minimum screen resolution 800 X 600.

2.2 Accessing User's Guides for PC*MILER Products

NOTE: You must have Adobe Acrobat Reader on your PC to properly view a PC*MILER product's user guide. If you do not have this program installed already, a free copy can be downloaded from www.adobe.com.

To make Adobe Reader your default reader, from within the Adobe Reader application:

1. Select the Edit menu > Preferences > General.
2. Click **Select Default PDF Handler**.
3. Select Adobe Reader from the drop-down.
4. Click **Apply**.
5. Click **OK** to close the Preferences dialog.

To view the user guide for any PC*MILER product on your PC without first opening an application, click the Windows **Start** button > **All Programs** (or the equivalent on your system) > **PCMILER 30** > and select one of the .pdf files.

To search for a keyword or phrase in a user guide, use Adobe Reader's **Find** option in the Edit menu or on the tool bar.

All user guides can also be accessed at www.pcmiler.com/support.

3.0 Installation

NOTE for Upgrading Users: There have been no changes to the ALKWIN or ALKTLL libraries since the Version 20 release. There is no need to upgrade your ALK library if you are currently running the Version 20 library. You can check to see if you are running the latest library by running `alkwin/pcmiler` or `alktll/pcmtll` commands and looking for the existence of Borders Open/Closed and Use Ferry Distance Options, and a single red • (period or dot) in the lower right hand corner of the screen at line 24, position 75.

```

Session A - [24 x 80]
File Edit Transfer Appearance Communication Assist Window Help
PrtScrn Copy Paste Send Recv Display Color Map Record Stop Play Quit Clipbrd Support Index

PCMiler 28.0

MI Request Type (MI - SM - HS)                                {Extended Routing Types}
P Routing Type (P=Prac - S=Short)                            - Toll Discouraged - National/53Ft
  Hub or Optimize (H R F or Blank)                          (T - Blank) (N=Ntnl 5=53ft Blank)
C Borders - O(pen) C(losed)
  Custom Routing - C(ustom)-Blank
N Ovrdr Restrictions (Y or N)
M Miles or Kilometers (M or K)                               HazMat G,C,E,F,I or R
Y Use Ferry Distance (Y or N)                               Worldwide N A,E,F,N,O,S (Continent)

Enter City,State,County or Zip (Press Help key for examples)

1 .....
2 .....
3 .....
4 .....
5 .....
6 .....
7 .....
8 .....
9 .....
10 .....

F2=State help F3=Exit F7=Ins stop F8=Del stop
F10=Process F11=Restart F22=Swap stops F23=Load Trip F24=Sav Trip
M a 13/011
Connected to remote server/host 10.60.115.230 using port 23

```

NOTE for Upgrades with PC*MILER|Tolls: You cannot use any existing ALKWIN library if you install PC*MILER|Tolls. You must use the ALKTLL library.

PC*MILER for the AS400 works by connecting a Windows PC to your AS400. The PC provides mileage lookups to the AS400 via data queues. Generally, there is one common input or request queue that all users write

to, with each user having their own output queue. The PC listens to the input queue for mileage request packets. Within each mileage request packet is the name of the user's output queue. The PC does a destructive read of the request packet, processes the request, and writes to the specified user's output queue.

PC*MILER for the AS400 was developed using the data queue facilities of IBM's Client Access Express. You must have this connectivity product installed and properly configured on the mileage server PC.

3.1 Installation Overview

You should have received one DVD and one CD with your purchase of PC*MILER-AS400, or one DVD and two CD's if PC*MILER|Tolls was purchased:

- The PC*MILER Product Line DVD which includes the complete PC*MILER application and the AS400 Mileage Server.
- The CD contains the 400 side ALKWIN Library.
- PC*MILER|Tolls users receive a second CD with the AS400-side ALKTLL Library.
- **NOTE:** ALKWIN is for use with PC*MILER and PC*MILER|Streets without the PC*MILER|Tolls add-on installed. ALKTLL is used for any installation that includes the Tolls component. PC*MILER|Tolls users will also receive the ALKWIN Library, which is only to be used when the PC*MILER|Tolls add-on is not to be installed.

NOTE: Required PC to AS400 Connectivity Software is not provided by ALK. You need IBM's Client Access Express.

3.2 AS400 Side Installation

First install the resident AS400 software on your AS400. Sign on to QSECOFR or an account with equivalent authorities. Place the CD in the optical drive and follow the instructions below.

NOTES For Upgrades: If you are upgrading your ALKWIN or ALKTLL Library from an earlier version, it is recommended that you **rename** your current ALKWIN [or ALKTLL] Library or clear your current library with the CLRLIB command.

Before clearing your current library, type 'config' or 'tlfig' from the AS400 command line and write down your current default settings. These settings will be overwritten during the library restore. After the restore of the library, re-enter these settings by running the ALKWIN/CONFIG command.

For Version 16 and Higher: ALK increased the length of the Highway Segment (HS – Turn-by-Turn Driving Instructions) by 25 characters. Failure to upgrade your current ALKWIN Library from pre-Version 16 will cause the program to crash if HS requests are used.

1. Create a library with the CRTLIB command. Type **CRTLIB ALKWIN** [or **ALKTLL**].

2. Add the library to the current library list. Type **ADDLIBLE ALKWIN** [or **ALKTLL**].

*(Statements in the following paragraph do not apply for installations that include PC*MILER|Tolls.)*

For Innovative Computing Corporation installations, you will also need your ICC WORK and FILE libraries in your current library list. For Version R6, type **ADDLIBLE I93FILE** or **ITSR6FILE** and then **ADDLIBLE I93WORK** or **ITSR6WORK**. The ICC Version 7 libraries are **IESR7WORK** and **IESR7FILE**. (Call ICC if you don't know which version you are running.)

3. Command for restoring from CD:

```
rstlib savlib(alkwin) dev(opt02) vol(alkwin) mbropt(*all)
alwobjdif(*all) rstlib(alkwin)
```

or

```
rstlib savlib(alktll) dev(opt02) vol(alktll) mbropt(*all)
alwobjdif(*all) rstlib(alktll)
```

where **opt02** is your CD-ROM drive.

Make sure all objects were restored. You can ignore security warning messages. It is okay if MIDQUE does not restore because this file is created later on.

NOTE: The ALKWIN [or ALKTLL] Library CD was created using Kisco Information Systems' BlueCD, which allows you to create AS400 readable SAVLIBs on a PC CD writer. A small percentage of users

may have difficulty restoring the ALKWIN [or ALKTLL] Library with the above command. If you experience problems.

Type **RSTLIB**, then:

- a. Specify the library ALKWIN [or ALKTLL] and the appropriate optical device
 - b. Press **<F10>** for more options
 - c. Specify ***ALL** on database member options
 - d. Specify ***ALL** on allow object differences.
4. The system administrator should make the library ALKWIN or ALKTLL available to users at sign-on time. There are two ways to insert ALKWIN [or ALKTLL] into the library list:
- a. The WRKSYSVAL command can be used by typing **WRKSYSVAL**, and then searching for the QUSRLIBL entry. Insert ALKWIN [or ALKTLL].
 - b. If your users are using a job description in their user profiles, then use the CHGJOB command (type **CHGJOB**) and insert ALKWIN or ALKTLL.

For Innovative Computing installations, a command is available to help insert a library into the library list. ALKWIN should be the first library in the library list. (**NOTE: Run this command from a typical ICC user account or profile, not QSECOFR**). Enter the following:

```
ADDLIBLE ILPGMR *LAST
CHGLIBLS
(insert) ALKWIN [or ALKTLL]
```

5. To grant object authority to library ALKWIN, enter the following:

```
GRTOBJAUT (press <F4>)
object = *ALL
library = ALKWIN [or ALKTLL]
objtype = *ALL
users = *public
authority = *ALL
```

NOTE: For ICC Users only (Be sure to do this!) Type config from the AS400 command line after the restore of the library and change the library for the location of mileage data queues from ALKWIN to your ICC Work library and change the ICC Support Short Code names flag from 'N' to 'Y'. Depending on the version of your ICC software your library will be I93WORK, ITSR6WORK, or

IESR7WORK. Check with ICC for this name. For ICC R8 and multiple company installations use ALKWIN. Do not configure an installation that includes the PC*MILER|Tolls component to point at an ALKWIN or ICC library.

NOTE Also: The AS400 side and the PC Side must match which Library the Mileage Request or Input data queue resides in. You will be prompted during the PC Side Installation for your data queue location or there is an option to change it under the PC*MILER-AS400 Control Menu which is an option in the File drop down menu.

The screenshot shows a terminal window titled "Session A - [24 x 80]" with a menu bar (File, Edit, Transfer, Appearance, Communication, Assist, Window, Help) and a toolbar. The main content is a green-on-black terminal display for "PC*MILER PARAMETER DEFAULTS".

The terminal text includes:

```

PC*MILER PARAMETER DEFAULTS
Press HELP for Item Descriptions

Request Type . . . MI MI=Miles - SM=State Totals - HS=Directions
Routing Type . . . P P(Practical) S(Shortest)
Toll Discouraged . T(Toll) or Blank
National/53 Foot . N(National) 5(53 Foot) or Blank
Custom Routing . . C (Custom) Blank (Default)
Hub or Optimize . . H(Hub) R(Route Through All) F (Fixed Destination)
Ovrd Restrictions. . Y or N . . . (Override Heavy Truck Restrictions)
Miles / Kilometers M or K
HazMat Type . . . G, C, E, F, I or R . . (Add-On Data Module)
Region(Continent). . N A, E, F, N, O, or S (Worldwide Version)
Borders . . . C 0(Open) - C(Closed)
Ferry Distance . . Y Y or N (Include Ferry Miles In Distance Totals)
These Mileage Parameters Will Be Stored For All Users On The System

Library name where mileage requests will reside. ALKWIN ICC Users this will be your
ICC WORK lib ie: IESR7WORK


Support ICC short code names N Y or N

F3=Exit without saving Press ENTER to save for all users
    
```

A white callout box with the text "Input Data Queue Library" has an arrow pointing to the "Library name where mileage requests will reside" line in the terminal.

At the bottom of the terminal window, it shows "M a" on the left, "04/023" on the right, and "Connected to remote server/host 10.60.115.230 using port 23" at the very bottom.

For Tolls:



3.3 PC Side Installation


STEP 1:

Make sure that Client Access Express is installed and working on the PC (see *Appendix D: Configuring Client Access Express for Use with PC*MILER-AS400*).

STEP 2:

Insert the Product Line **INSTALL DVD** into your DVD drive, or click the link that was sent to you via email from ALK Technologies.

Start the installation by double clicking the 'Install_PCMILER_30' shortcut or you can launch the setup.exe from within the 'Installation Files' folder.



When you are prompted, enter the **Product Key Code** that was e-mailed to you at the time of purchase. Your product code will be in this format:

XXXXX-XXXXX-XXXXX-XXXXX-XXXXX

When entering the Product Key Code, dashes are not required – dashes, spaces, or no spaces are all acceptable.


If you do not have your Product Key Code, call ALK Technologies at **800-377-6453 ext. 2** from **8:00am to 5:00pm** EST Monday through Friday. The Product Key Code unlocks the products you purchased – either PC*MILER or PC*MILER|Streets and the AS400 Mileage Server (PC*MILER-AS400). **Both these components should appear in the Licensed Features screen** (shown on the next page) that displays after you enter your Product Key Code and click **Next**.

NOTE for users upgrading from an installation of ALK|FleetSuite Tolls: For the AS400 you will need the PC*MILER|Tolls component as shown on the next page.


NOTE: If you are using PC*MILER-AS400 with any third party or custom in-house software package, you CANNOT install the PC*MILER|Tolls component as circled above without modifying that software. To use the enlarged Tolls Cost data structures, see *Chapter 7* and *Appendix H* for more information.

NOTE: As of 5/7/07, Innovative Computing Corporation (ICC) has not released a version of their software that works with the PC*MILER|Tolls component. ICC users should not install PC*MILER|Tolls if they intend to use this installation in conjunction with their ICC software.


“Licensed Features” Screen for PC*MILER:



“Licensed Features” Screen for PC*MILER|Streets:



“Licensed Features” Screen for PC*MILER|Tolls:




Click **Next** and in the next screen select a folder to install to, or use the default folder (**PCMILER30**). Click **Next** again when ready.

Note: Installing to a folder called PCMILER30 is required. Do not rename the folder after installing.

During the installation you will be prompted to enter the name of the library for data queues. The default values are **ALKWIN** (without PC*MILER|Tolls) and **ALKTLL** (with PC*MILER|Tolls). **NOTE:** ICC users need to coordinate with Innovative to enter the proper ICC Work Library for their release of the ICC software. Upgrading ICC users can read the correct library by running the `alkwin/config` command from an AS400 command line.


If you purchased the PC*MILER|Tolls component you will get the following prompt:



Answering '**Yes**' will turn off the Tolls component and install an ICC-compatible version of the PC Mileage Server.

Answering 'No' will install the PC*MILER|Tolls version of the PC Mileage Server. (ICC users and users of third-party or custom in-house transportation software should click 'Yes' and refer to *Appendix H* and Chapter 7 for instructions about using PC*MILER|Tolls with their software.)

Library for Data Queue Locations:



PC*MILER 30 - Main Software InstallShield Wizard

Data Queue Library


Please enter Library where data queues are stored.
This should match the library specified by the AS400 CONFIG command

ALKWIN

InstallShield

< Back Next > Cancel

Library for Data Queue Locations with PC*MILER|Tolls:



PC*MILER 30 - Main Software InstallShield Wizard

Data Queue Library


Please enter Library where data queues are stored.
This should match the library specified by the AS400 CONFIG command

ALKTLL

InstallShield

< Back Next > Cancel

When entering your system and sign-on information, if possible use the **IP address** rather than the System Name of your AS400. **Be careful that the password for the User Profile that you specify is set not to expire.** Your User Profile must have the authority to create and delete data queues in the library that you specified in the previous dialog.




The screenshot shows a Windows-style dialog box titled "PC*MILER 30 - Main Software InstallShield Wizard". The window has a blue header bar with the title and a close button. Below the header, the text "User Information" is displayed. To the right of the text is the PC*MILER logo, which consists of a blue shield with a white 'P' and 'M' and the text "PC*MILER" next to it. Below the logo, there is a message: "In order to enable automatic sign-on to your AS/400 machine, PC*MILER AS/400 Interface needs the following information". There are three input fields: "System" with the placeholder text "<IP Address or System Name of Your AS400>", "User" with the placeholder text "<User Profile Distance Server Will Signon With>", and "Password:" with the placeholder text "<Password for Above User Profile>". At the bottom left, the text "InstallShield" is visible. At the bottom right, there are three buttons: "< Back", "Next >", and "Cancel".

STEP 3:

You must activate your installation within 15 days of installing. If your PC has internet access this is an automated process. If your PC does not have internet access, you will have to contact ALK to receive your activation code.

Both types of activation are described on the following pages. **Note:** There is no AS400 side licensing.



To activate immediately, leave **Activate license** checked and click **Finish** to open the ALK License Manager. (To activate at a later time, uncheck the **Activate license** check box. Each time you open PC*MILER for the next 15 days, the ALK License Manager will pop up, giving you another chance to activate the software. Or you can select *Programs > PCMILER 30 > License Status* in the Windows **Start** menu.)



NOTE: The 15-day grace period for activation is only available for the first installation of Version 30 on your PC. If you are reinstalling for any reason you will have to activate the installation before it can be used.

Automatic License Activation:

Click **Activate** in the License Manager. The rest of the process is completely automated if you have internet access on your PC. You will see the message "License Activation Complete!" when the activation is finished. Close the Product Activation window, then click the Windows **Start** menu > *Programs* > *PCMILER 30* > *License Status* and make sure that "Licensed" appears under **Status** in the PC*MILER License Tool window. If so, PC*MILER is now permanently licensed.



Manual Activation:

If the Automatic Activation process fails due to firewall security settings or for any other reason, try activating manually. Check the **Manual Activation** box. In the Manual Activation screen that appears, click the <http://activate.alk.com> link to open a webpage that will provide you with an activation code 24/7. You may need to add <http://activate.alk.com> or <https://activate.alk.com> as a trusted site to get the activation webpage to open. Enter the Activation Code, then click **Activate**. **Note:** You can get access to this screen after the initial installation by clicking the Windows **Start** menu > *Programs* > *PCMILER 30* > *License Status* and then clicking the Activate button.

The screenshot shows a window titled "PC*MILER Product Activation" with a "Manual Activation" section. The instructions are as follows:

- Go to the following URL to obtain an activation code.
<http://activate.alk.com/ALKActivation.aspx> (labeled "Web page link")

Product Key:
KT4L2-3B2AE-437LT-2375K-T8263

License #: 750815C6 (circled in red and labeled "License Number")

- Enter the activation code below
Activation Code:
[Empty text box]


Manual Activation (labeled "Check 'Manual Activation'")

Activate

Manual Activation on a PC Without Internet Access:

Call ALK's Technical Support during business hours (see section 10.0) and give your technical support representative the license number from the Manual Activation screen or the License Tool window. You'll receive an activation code, which you can then enter in the Manual Activation screen. Click **Activate** to complete the process.

When the activation process is complete, a "License Activation Complete!" message will appear in the Product Activation window. Click the Windows **Start** menu, then *Programs > PCMILER 30 > License Status* and make sure that "Licensed" appears under **Status** in the PC*MILER License Tool window. If so, PC*MILER is now permanently licensed. If not, call Technical Support (see section 10.0).



3.4 Creation of Desktop Icons

During the installation of the PC*MILER for the AS400 interface software on the PC, an icon to start the mileage server is placed in the startup folder. If you want to have a desktop icon, you can do a right mouse click Copy, and then a right mouse click Paste Shortcut onto the desktop.

To do this after the initial installation, right mouse click the **Start** menu; choose **Open All Users** (or **Open** on some systems); double-click the **Programs** folder; double-click the **Startup** icon; then use the right mouse button to Copy and Paste Shortcut on the desktop.

If you create a desktop icon any other way, the command line or target has to read as shown below. **INCORRECT ICON PROPERTIES can cause the mileage server not to start or to return incorrectly formatted mileage!**

For PC*MILER:

C:\ALK Technologies\pcmiler30\as400\SRV32.exe
 <space>1<space>2<space>1 for NS Router Connections

C:\ALK Technologies\pcmiler30\as400\SRV32.exe
 <space>1<space>2<space>2 for Client Access Express Connections


For PC*MILER|Streets:

C:\ALK Technologies\pcmiler30\as400\SRV32.exe <space>2<space>2
 <space>1 for NS Router Connections

C:\ALK Technologies\pcmiler30\as400\ SRV32.exe
 <space>2<space>2 <space>2 for Client Access Express Connections

NOTE: Shortcuts are unchanged with PC*MILER|Tolls installed.


NOTE: On some systems you will have to run Srv32.exe as an Administrator. The following error is a symptom that this setting is required.



To make this setting do the following:

1. Right mouse click on C:\ALK Technologies\PCMILER30\AS400\Srv32.exe.

2. Choose 'Properties'.
3. In the 'Compatibility' tab check 'Run this program as administrator' in the 'Privilege Section' as below:




4.0 Starting and Stopping the Mileage Server

4.1 Starting the Mileage Server

The software you installed on your dedicated PC will cause the interface to start automatically when the PC is turned on. You can launch the Mileage Server without restarting the PC by clicking Start menu > Programs > PCMILER 30 > AS400 Interface.

When the mileage server (**SRV32.exe**) starts, it displays the connection status in the mileage server's log window. You can bring up this window by clicking on the mileage server's **Window** Menu and choosing *Display Server Log*.



The Name of Mileage Request or Input data queue, and the library in which the queue resides, are logged.

The number underneath the data queue name and library is the connection status return code. Good returns are:

- 0 Connection Good Created Data Queue**
- 2 Connection Good Found Data Queue**

Return codes of 1 or 3 are generic error codes that indicate problems with your Client Access Express connection.

NOTE: Both the PC and the AS400 must agree on the location of the Input or Request data queue. To change the location on the PC, click on the mileage server's **File** menu. Choose *AS400 Control*, then *Change Library/Queue*. The change is made on the AS400 by running the **alkwin/config** or **alktl/tlfig** command and filling out the library field.

The server log only notes incoming requests. If you need to see the mileage server's outputs, turn on the Log to File feature by selecting the mileage server's **File** menu and choosing *AS400 Control > Log to File* and highlight *Append*, *Overwrite* or *Verbose* (see below). This will create the file **c:\ALK Technologies\pcmiler30\as400\as400.log**. It is recommended to only use logging for diagnostic purposes, otherwise the log files tend to grow large.

- **Append** will add to the existing as400.log file after restarts.
- **Overwrite** will delete the existing as400.log file after restarts.
- **Verbose** logging includes information from the data queue communications. Verbose logging Appends after restarts.

4.2 Stopping the Interface

From the PC*MILER-AS400 window, choose **Exit** from the **File** menu.

4.3 Configuring the Use of Mexican Postal Codes

Version 30 of PC*MILER includes over 25,000 Mexican postal codes in the database that provide comprehensive coverage of Mexico. Mexico and the United States use the same five-digit numbering scheme for their postal codes. The two countries share a large number of common codes and care must be taken so that users do not accidentally match a Postal or ZIP code to the wrong country. By default, all Mexican postal codes are ignored.

To turn on access to Mexican postal codes, click the **File** dropdown menu, choose **AS400 Control** and then **Default Zip Codes** and highlight your choice.

Choose between:

- **Use default US Zip Code:** This is the default setting. All Mexican postal codes will be ignored.
- **Use default Mexican Zip Code:** Turns on the use of Mexican postal codes. If a user specifies only a five-digit Postal or ZIP code as a stop, the trip will be routed to Mexico in cases where there are duplicate codes between the US and Mexico.
- **Use default US and Mexican Zip Code:** The default U.S. ZIP code or Mexican postal code will be returned. If there are U.S. and Mexican codes with the same number, the default U.S. ZIP code will be returned. If there is only a Mexican postal code for that number, the default Mexican code will be returned.

The default for this setting can be changed in the PCMSERVE.INI file (see *Appendix F*). If they are not already there, these lines can be added to the [OPTIONS] section. The possible setting combinations are:

- UseUSPostCodes=False and UseMexPostCodes=False – Defaults to the U.S. ZIP with no routing to Mexican postal codes
- UseUSPostCodes=True and UseMexPostCodes=False – Same as above
- UseUSPostCodes=True and UseMexPostCodes=True – Defaults to the U.S. ZIP, must pass an Estados code to get Mexican location (e.g. "50510,EM")
- UseUSPostCodes=False and UseMexPostCodes=True – Only Mexican postal codes are available, in the U.S. only city-state pairs will get U.S. location (e.g. "Chico, CA")

5.0 Using PC*MILER for the AS400

To use PC*MILER for the AS400, issue the command **PCMILER** (or **PCMTLL** for PC*MILER|Tolls) from the command line.

PCMILER Main Screen:

```

Session A - [24 x 80]
File Edit View Communication Actions Window Help
PCMiler 30.0

HS Request Type (MI - SM - HS)
P Routing Type (P=Prac - S=Short)
- Hub or Optimize (H,R,F or Blank)
C Borders - 0(pen) C(losed)
- Custom Routing - C(ustom)-Blank
Y Ovrdr Restrictions (Y or N)
M Miles or Kilometers (M or K)
Y Use Ferry Distance (Y or N)

{Extended Routing Types}
- Toll Discouraged - National/53Ft
(T - Blank) (N=Ntnl 5=53ft Blank)

{Add-On Products}
HazMat - G,C,E,F,I or R
Worldwide N A,E,F,N,O,S (Continent)

Enter City,State,County or Zip (Press Help key for examples)
1 ..... Margo, VA, Spotsylvania
2 ..... 25235 Chloe, WV, Calhoun
3 ..... Debs, MN, Beltrami
4 ..... Kittys Corner, MD, Talbot
5 ..... Andrew, FL, Leon
6 .....
7 .....
8 .....
9 .....
10 .....

F2=State help F3=Exit F7=Ins stop F8=Del stop
F10=Process F11=Restart F22=Swap stops F23=Load Trip F24=Sav Trip
MA A MW 13/011

```

NOTE: The PCMILER or PCMTLL command contacts the mileage server to read the data that the mileage server is using. If the command doesn't respond or the PC*MILER screen comes up with "PC DOWN" in the screen title, there is a problem with the connection to the mileage server PC.

PCMTLL Main Screen:

The screenshot shows the PCMTLL Main Screen with the following control settings and city list:

```

PCMTLL Main Screen:
Title: Session B - [24 x 80]
Menu: File Edit View Communication Actions Window Help
Title Bar: PCMiler Tolls 30.0
Content:
MI Request Type (MI - SM - HS) {Extended Routing Types}
P Routing Type (P=Prac - S=Short) 5 National/53Foot - Toll Discouraged
C Toll Cost (T=Cash - D(iscount) (N=Ntnl 5=53ft Blank) (T or Blank)
Y Borders - 0(pen) C(losed)
Y Use Ferry Distance (Y or N) {Add-On Products}
M Hub or Optimize (H,R,F or Blank) HazMat . - G,C,E,F,I or R
M Miles or Kilometers (M or K) Worldwide N A,E,F,N,O,S (Continent)
N Custom Routing (C=Custom or Blank)
N Ovrdr Rstrctions (Y or N)

Enter City,State,County or Zip (Press Help key for examples)
1 ..... 25235 Chloe, WV, Calhoun
2 ..... Kittys Corner, MD, Talbot
3 ..... Margo, VA, Spotsylvania
4 ..... Debs, MN, Beltrami
5 ..... Andrew, FL, Leon
6 .....
7 .....
8 .....
9 .....
10 .....
F2=State help F3=Exit F7=Ins stop F8=Del stop
F10=Process F11=Restart F22=Swap stops F23=Load Trip F24=Sav Trip
MA B 03/003

```

Control settings at the top of the main entry screen include the following:

Request Type: "MI", the default entry, will generate only point-to-point mileage look-ups. "SM" will generate a summary of miles traveled through each state, broken down by toll roads and free roads, in addition to the point-to-point mileage. "HS" will generate detailed driving instructions, in addition to the state mileage summary and point-to-point mileage look-up.

Routing Type: Either Practical or Shortest routing can now be combined with other available PC*MILER routing options (Toll Discouraged, National Network, or 53' Trailer or Twins). You must specify either P (Practical) or S (Shortest) for all routes. (Refer to the main PC*MILER *User's Guide* for more detailed descriptions of these routing options.) See Chapter 6, *Using PC*MILER With Other Transportation Software* for details on using this functionality with other software packages.

NOTE: For Version 30, the 53 Foot Trailer routing option has been replaced with the 'State + National Network' routing option to better reflect the combination in previous versions of PC*MILER's National Network and 53 Foot Trailer Networks when the 53 Foot Trailer option was selected. The interactive green screen PC*MILER program has not be updated to reflect the change. Choosing either the 53 Foot Trailer or National Network Extended Routing option will turn on the State + National Network option.

Tolls Cost: (Only with PC*MILER|Tolls installed) "T" will generate the Cash cost of all tolls incurred on a trip. "D" will give the Discounted toll cost. See Appendix J, *Setting Toll Discount Program Membership*, for instructions on configuring your discount memberships. Depending on the request type used, you will get total toll costs for the entire trip, a state-by-state breakdown of toll costs, or the toll cost per leg of the trip.

NOTE: PC*MILER|Tolls calculates tolls for an 80,000 pound, 5-axle vehicle. Reported toll amounts are accurate and up-to-date, but not always exact due to two factors: first, several – though not many – toll roads have rates that are based on weight (for example, the Detroit-Windsor Tunnel charges \$.03 per 100 lbs. gross weight in both directions); and second, some toll charges (in various states) are time-of-day driven. In the latter case, tolls will always be calculated using the highest rate.

Toll Discouraged: "T" will generate miles which avoid long stretches of toll roads. You will receive either a Practical Toll Discouraged Route, or a Shortest Toll Discouraged Route depending on how you have your "Routing Type" set. Note that not all toll roads will be avoided; tolls are avoided where possible while still maintaining a reasonable and practical route.

National/53 Foot: Either "N" or "5" will generate miles calculated using the State + National Network which favors the US Federally designated National Network (primary Interstates with reasonable entry/egress points up to 1 mile off the Interstate) and state designated extensions to the National Network (additional highways and supporting roads any distance off the Interstate, as determined by individual states). State + National Network (National Network or 53 Foot Trailer or Twins) will be generated using either the "Practical" or "Shortest" routing type. You can also combine State + National Network (National Network and 53 Foot Trailer or Twins) routing with the Toll Discouraged option. For example you can generate a "Practical/Toll Discouraged/National Network" route. See Chapter 6, *Using PC*MILER With Other Transportation Software* for details on using this functionality with other software packages.

Custom Routing: "C" will use custom routing preferences (avoids and favors) set in PC*MILER or PC*MILER|Streets. When this position is blank, routing preferences will be disabled.

Hub or Optimize: A blank space is the default entry and is used for standard PC*MILER routing. "H" is used to generate hub distances. "R" is used to initiate route sequencing with the origin fixed and the remaining stops reordered. "F" is used to initiate route sequencing with both the origin and destination fixed and the remaining stops reordered. These options are described in more detail in the main PC*MILER *User's Guide*.

Borders: "O" will open the borders and routes will cross International Borders to obtain the most efficient trip. "C" will close the borders and routes will only cross international borders if the trip has a stop in that country.

Ovrd (Override) Restrictions: In addition to the five basic PC*MILER route types, a Heavy and Light Vehicle routing option is now offered. When Ovrd Restrictions is set to "Y", the **Light Vehicle** option is activated. With Light Vehicle routing active, truck-prohibited roads will always be avoided, but truck-restricted roads are considered for a route. (PC*MILER normally gives preference to Interstates, major highways, and major thru-roads where possible.)

NOTE: With Ovrd Restrictions set to "N", **Heavy Vehicle** routing is in effect, so both **truck-prohibited and truck-restricted roads will always be avoided**. In addition, Heavy Vehicle routing takes nationwide **13' 6" height restrictions** into account. A heavy vehicle is one weighing at least **80,000 pounds**; a light vehicle weighs less than **80,000 pounds**.

Miles/Kilometers: "M" will generate distances in miles. "K" will generate distances in kilometers.

Use Ferry Distance: If set to "Y", distance traveled on ferries will be included in all distance totals. If set to "N" ferry distances are not included in totals. Note: Routes will still include ferry travel but this travel is not included in distance totals.

HazMat (Hazardous Material Type): *(only with the PC*MILER|HazMat add-on data module installed)* Types of hazardous material routing that can be generated are: "G" for General, "C" for Corrosive, "E" for explosive, "F" for Flammable, "I" for Inhalant, and "R" for Radioactive.

Region (Continent): Regions in which mileage can be generated are: "A" for Asia; "E" for Europe; "F" for Africa; "N" for North America; "O" for

Oceania; or "S" for South America. (Regions outside North America require PC*MILER|Worldwide.)

FOR AN ON-SCREEN DISPLAY OF THESE DEFINITIONS, press the Help key on your keyboard. For Terminal Emulation sessions on PC's, this is typically the **Scroll Lock key or Right Mouse Click > Help**.

In the middle of the screen are the stop entry fields. Enter the city names and state abbreviations for the stop-off locations desired, their ZIP codes, or their latitude/longitude positions. Both the Spelling Helper and ZIP Code Helper described in the main PC*MILER *User's Guide* are available for use with PC*MILER-AS400. You may enter up to 30 stop-offs.

NOTE for PC*MILER|Streets Users: An address should directly follow the city/state or ZIP code entry, separated by a semicolon (e.g. "Princeton, NJ; 457 North Harrison Street").

You can also purchase separate add-on data modules for Canadian postal codes or SPLC codes.

A **Canadian postal code** is entered in the same manner as a ZIP code, but in the following format: **L#L<space> #L#**. (e.g. "K7L 4E7"). A **SPLC** is a six- or nine-digit number, preceded by the letters 'SPLC' (e.g. "SPLC908601").

5.1 Function Keys

At the bottom of the screen, the function keys used with PC*MILER for the AS400 are described. These include:

- F2 State help.** Displays a list of all state and province abbreviations.
- F3 Exit.** Exits the program and returns to the main AS400 screen.
- F7 Ins stop.** Allows you to insert a new stop-off where the cursor is positioned.
- F8 Del stop.** Allows you to delete a stop-off where the cursor is positioned.
- F10 Process request.** Sends the request to PC*MILER on the dedicated PC.
- F11 Restart.** Clears the screen, and lets you start making data entries on the screen again.
- F12 Main Screen.** Returns to the main stop entry screen from the mileage report screens.
- F22 Reverse.** Reverses the order of stops entered.
- F23 Load a saved trip.** In the screen that comes up, typing "X" (with the cursor on a trip identifier in the pick list) will load that trip; typing "D" will delete the trip.
- F24 Save a trip.** Enter a trip identifier of up to 10 characters in the entry field that appears.
- Help** Pressing the key labeled "**Help**" on your keyboard will bring up detailed instructions for using various features of PC*MILER for the AS400. If you are using an emulator, the Help key on your keyboard will usually be the **Scroll Lock** key or **Right Mouse Click > Help**.

5.2 Basic Mileage, Cost and Time Report

Once you have entered stops on the main screen and initiated a mileage inquiry by pressing <F10>, the following basic mileage screen will appear:

	MILES	CUM	TIME	COST
Margo, VA, Spotsylvania				
25235 Chloe, WV, Calhoun	297	297	5.1	340.64
Debs, MN, Beltrami	1159	1456	19.2	1341.56
Kittys Corner, MD, Talbot	1403	2859	22.5	1765.69
Andrew, FL, Leon	895	3754	14.4	987.52
Total:	3754		61.2	4435.41

F3=Exit F4=State Miles F8=Directions F9=Print
 F11=Restart F12=Main Scrn F15=Save Route

Mâ A MW 01/072

With PC*MILER|Tolls Installed:

Session B - [24 x 80] File Edit View Communication Actions Window Help

PCMiller Tolls 30.0 6/03/16
01:40:34

	<u>MILES</u>	<u>CUM</u>	<u>TIME</u>	<u>COST</u>	<u>CUM TOLL \$</u>
25235 Chloe, WV, Calhoun					
Kittys Corner, MD, Talbot	393	393	6.2	453.63	24.00
Margo, VA, Spotsylvania	154	547	2.6	175.14	24.00
Debs, MN, Beltrami	1437	1984	23.3	1647.44	81.00
Andrew, FL, Leon	1602	3586	25.7	1769.04	88.50
Total:	3586		57.8	4045.25	88.50

F3=Exit F9=Print
F11=Restart F12=Main Scrn

MA B 01/072

This basic PC*MILER mileage report contains leg and cumulative miles for each segment of your trip. The time and cost estimates are based on the values set in the copy of PC*MILER (or PC*MILER|Streets) installed on your dedicated PC. (Refer to the main PC*MILER *User's Guide* for instructions on how to alter these values.)

NOTE: The leg costs and total cost in the “**COST**” column **include** toll costs if PC*MILER|Tolls is installed.

<F3> will exit the program. <F9> will print the screen. <F11> will return you to the previous screen and will clear it. <F12> will return you to the previous screen, without clearing it.

5.3 State Mileage Report

After you enter stops on the main screen and initiate a state mileage request (**SM**) by pressing **<F10>**, the basic mileage screen will appear:

	MILES	CUM	TIME	COST
Margo, VA, Spotsylvania	297	297	5.1	340.64
25235 Chloe, WV, Calhoun	1159	1456	19.2	1341.56
Debs, MN, Beltrami	1403	2859	22.5	1765.69
Kittys Corner, MD, Talbot	895	3754	14.4	987.52
Andrew, FL, Leon	895	3754	14.4	987.52
Total:	3754		61.2	4435.41

F3=Exit F4=State Miles F9=Print
 F11=Restart F12=Main Scrn

MR A MW 01/072

With PC*MILER|Tolls Installed (costs in the "COST" column include tolls):

PC*MILER Tolls 30.0 6/03/16
02:05:39

	MILES	CUM	TIME	COST	CUM TOLL \$
25235 Chloe, WV, Calhoun					
Kittys Corner, MD, Talbot	393	393	6.2	453.63	24.00
Margo, VA, Spotsylvania	154	547	2.6	175.14	24.00
Debs, MN, Beltrami	1437	1984	23.3	1647.44	81.00
Andrew, FL, Leon	1602	3586	25.7	1769.04	88.50
Total:	3586		57.8	4045.25	88.50

F3=Exit F4=State Miles F9=Print
F11=Restart F12=Main Scrn

MA B 01/072

Pressing <F4> displays Jurisdiction-by-Jurisdiction distance breakdowns:

PC*MILER 30.0 6/01/16
02:06:45

State Mileage Summary

STATE	MILES	TOLL	STATE	MILES	TOLL	STATE	MILES	TOLL
DC								
FL	31		NON TOLL	3035				
GA	230		TOTAL:	3754	719			
IL	237	200						
IN	384	108						
MD	228	6						
MN	359							
NC	181							
OH	420	241						
PA	187	164						
SC	199							
VA	353							
WI	743							
WV	201							

F3=Exit F7=Miles F9=Print
F11=Restart F12=Main Scrn

MA A MW 06/002

With PC*MILER|Tolls Installed:

Session B - [24 x 80] PC*Miler Tolls 30.0 6/03/16
 File Edit View Communication Actions Window Help 02:08:12

State Mileage Summary

STATE	MILES	TOLL MILES	TOLL COST
AL	316		
DC			
FL	83		
IL	543	116	51.00
IN	231		
KY	93		
MD	325	6	24.00
MN	359		
OH	182		
TN	133		
VA	248		
WI	743		
WV	328	45	13.50
NON TOLL	3419		
TOTAL:	3586	167	88.50

F3=Exit F7=Miles F9=Print
 F11=Restart F12=Main Scrn

MA B 06/002

5.4 Detailed Driving Directions Report

After entering stops on the main screen and pressing <F10> to initiate a Detailed Driving Directions (HS) request, press <F8> in the mileage report screen to generate the driving directions. When processing is complete, the screen shown below will appear. Note that driving directions take significantly longer to process than miles or state miles because more information is requested and returned.

Session A - [24 x 80] File Edit View Communication Actions Window Help

PCMiler 30.0 6/01/16 02:08:47

Margo, VA, Spotsylvania To Andrew, FL, Leon
4 Stops, 3754 Miles

State	Route	Miles	Leg	Total
Origin: Margo, VA, Spotsylvania				
VA	S Local	1	+ Local VA-208	1
VA	W VA-208	12	+ VA-208 VA-208	13
VA	S VA-208	5	+ VA-208 VA-208	18
VA	W VA-208	6	+ VA-208 VA-208	24
VA	W VA-208	7	+ VA-208	30
VA	W VA-208	2	+ VA-208 Ramp	33
VA	R Ramp		+ Ramp I-64	33
VA	W I-64	55	+ I-64 Ramp	88
VA	Ramp	1	+ Ramp I-64	89
VA	W I-64	30	+ I-64 Exit 191	118
VA	Exit 191		+ Exit 191 I-64	119
VA	W I-64	40	+ I-64	159
VA	W I-64	17	(to VA/WV State Line)	175
WV	W I-64	3	+ I-64	179
WV	W I-64	24	+ I-64 Exit 156	203

F3=Exit F4=State Miles F7=Miles F9=Print
F11=Restart F12=Main Scrn F15=Save Route

MA A MW 06/002

A Detailed Driving Directions report with PC*MILER|Tolls installed is shown below. This sample report includes toll costs for each leg of the trip.

State		Route	Miles	Leg	Total
Origin: Margo, VA, Spotsylvania					
VA	S	Local	1	1	1
VA	W	VA-208	12	13	13
VA	S	VA-208	5	18	18
VA	W	VA-208	6	24	24
VA	W	VA-208	7	30	30
VA	W	VA-208	2	33	33
VA	R	Ramp		33	33
VA	W	I-64	55	88	88
VA		Ramp	1	89	89
VA	W	I-64	30	118	118
VA		Exit 191		119	119
VA	W	I-64	40	159	159
VA	W	I-64	17	175	175
WV	W	I-64	3	179	179
WV	W	I-64	24	203	203

F3=Exit F4=State Miles F7=Miles F9=Print
 F11=Restart F12=Main Scrn F15=Save Route

MA A MW 06/002

6.0 Using PC*MILER with other Transportation Software

NOTE for Version 21 and Higher: The following features are not supported in the AS400 product line: Estimated Greenhouse Gas Emissions, RouteSync, TripDirect, Entry/Exit Toll Plaza Names in Reports, and Real-time/Historical Traffic Data. Province/Estado Abbreviation Option to set "NL" preference is supported in Version 25-30 only.

Added to Version 20 and higher: Borders Open/Closed and Use Ferry Distance options. The first two characters of the four-character "Request Sequence" have been remapped to hold the Borders and Ferry Flags.

Historically the Request Sequence values have been ignored by the PC Distance Server. Unlike other trip options, Border and Ferry settings are not echoed back in the responses from the PC.

For the optional **PC*MILER|HazMat** hazardous material routing package, two routing types have been added: **Caustic** and **Flammable**.

REMINDER: *Users of PC*MILER Versions 14 and 15, and PC*MILER|Streets Versions 1, 2000, 3, and 4 must type a comma between the city and the state or province. For Version 16 and higher you have the option of using a comma or a space between the city and state or province abbreviation.*

NOTE: PC*MILER 18 and higher has full Mexican Estado information. Previously, all Mexican cities were referenced with 'MX' as the Estado code and the Estado was returned in the US county field. For example:

Older versions format: Mexico City, MX, Distrito Federal
Correct format for Version 18: Mexico City, DF

Estados Codes:

AG	Aguascalientes
BJ	Baja California
BS	Baja California Sur
CP	Campeche
CH	Chiapas
CI	Chihuahua
CU	Coahuila de Zaragoza
CL	Colima
DF	Distrito Federal
DG	Durango

GJ	Guanajuato
GR	Guerrero
HG	Hidalgo
JA	Jalisco
EM	Mexico (Estado)
MH	Michoacan de Ocampo
MR	Morelos
NA	Nayarit
New for 25=> NX* or NL	Nuevo Leon (PC Side Configuration Option – Tools menu)
OA	Oaxaca
PU	Puebla
QA	Queretaro Arteaga
QR	Quintana Roo
SL	San Luis Potosi
SI	Sinaloa
SO	Sonora
TA	Tabasco
TM	Tamaulipas
TL	Tlaxcala
VZ	Veracruz
YC	Yucatan
ZT	Zacatecas

* "NX" is used for Nuevo Leon because "NL" is already used in the database for the Canadian province of Newfoundland and Labrador. The option to configure NL for routing to Nuevo Leon is supported in Version 25-30 only.

ALSO NOTE: For Version 17 and higher the routing type options have changed for National Network, Toll Discouraged, and 53'/102" Trailer routing. These three routing options now can be generated in combination with the 'Practical' or 'Shortest' options. Additionally, National Network or 53' Trailer routing can be combined with the Toll Discouraged option. The only way to take advantage of this functionality is to pass in the new code in position 1 of the Request Options.

ALSO NOTE: For Version 30, the 53 Foot Trailer routing option has been replaced with the 'State + National Network' routing option to better reflect the combination in previous versions of PC*MILER's National Network and 53 Foot Trailer Networks when the 53 Foot Trailer option was selected. For Third Party applications, ALK will continue to support the use of either the 'N' or '5' Network Types to turn on State + National Network Routing. The following extended routing types will also turn on State + National Routing portion of the request:

C = National Network/Practical
D = 53 Foot Trailer/Practical
E = Toll Discouraged/National Network/Practical
F = Toll Discouraged/53 Foot Trailer/Practical
H = National Network/Shortest
I = 53 Foot Trailer/Shortest
J = Toll Discouraged/National Network/Shortest
K = Toll Discouraged/53 Foot Trailer/Shortest

Previously the five available codes were:

P = Practical
S = Shortest
N = National Network
T = Toll Discouraged
5 = 53 Foot Trailer

New Codes:

P = Practical
S = Shortest
B = Toll Discouraged/Practical
C = National Network/Practical
D = 53 Foot Trailer/Practical
E = Toll Discouraged/National Network/Practical
F = Toll Discouraged/53 Foot Trailer/Practical
G = Toll Discouraged/Shortest
H = National Network/Shortest
I = 53 Foot Trailer/Shortest
J = Toll Discouraged/National Network/Shortest
K = Toll Discouraged/53 Foot Trailer/Shortest

Use of the old codes is still supported, no changes are required. Old codes for National Network (N), Toll Discouraged (T), and 53 Foot Trailer (5) will be generated using the Practical network. Changing this default to the Shortest network is not possible.

NOTE: For users upgrading from PC*MILER|Streets, the Light/Heavy vehicle option has been renamed to 'Override Restrictions'. Parameter codes have changed from L (Light) to Y (Override Restrictions) and H (Heavy) to N (Obey Restrictions). Use of L and H is still supported.

NOTE: For Version 16 and higher, the HS (Turn-by-Turn Driving Instructions) return packet was changed from previous versions. The fields

for Route and Interchange were lengthened and the number of sets of route information was reduced from 4 sets per packet to 3. See section 6.2.4 for details.

6.1 Technical Overview

The PC*MILER-AS400 system uses distributed processing techniques (i.e. the processing is split into two). The user interface or interactive software is written in RPG and runs on the AS400. Small CL programs are used for the creation and removal of temporary data queues (output or response queues). The mileage calculation software is written in C++ and runs on a PC in the Windows environment.

The RPG programs communicate with the PC mileage calculation software through Client Access Express. The interactive software on the AS400 allows multiple users to look up point-to-point mileage and routes for up to thirty stop-off points. The Windows server application creates a data queue on the AS400 at startup called MIDQUE. The server application waits for mileage requests and processes them when received. While the server application is waiting for work to do, the PC can be used for other tasks such as PC*MILER graphics or RUMBA terminal emulation.

AS400 Programs

<i>Files</i>	<i>Description</i>
MIINQ	Main AS400 inquiry program that sends request to MIDQUE data queue
CITALK	RPG program that verifies city ZIP spelling
CRTQ	CL program that creates an output data queue based on the job number
DELQ	CL program that deletes the queue created by CRTQ
GETLAT	Sample RPG Program that converts City, Jurisdiction pairs or zip codes to Lat/longs
GETLATC	CL program that creates output queue and starts GETLAT RPG
GETMIL	Sample RPG Program performs point-to-point mileage lookups
GETMILC	CL program that creates output queue and starts GETMIL RPG
GETQNAME	RPG Program that determines library and data queue name for sending requests
VALDR	RPG Program that validates ZIP codes, place names, and street addresses; also provides pick lists of ZIP codes, names and addresses when partial name, ZIP or address is passed in RPG parameters.
MIDQUE	Data queue that contains input mileage lookup records
MIINQC	CL program that creates output data queue and starts MIINQ rpg
QUEUE	CL program that writes to the MIDQUE request data queue
MISEND	External data structure for sending mileage requests
MIRESP	External data structure for receiving mileage output
DRAW	External data structure for sending graphics requests to PC
MISEND2	External data structure with field mappings for Borders and Use Ferry Distance
TLSEND2	External data structure with field mappings for Borders and Use Ferry Distance

The program MIINQ contains two subroutines that can be used to integrate miles with other transportation software. The subroutine SNDREQ sends mileage requests to PC*MILER and the subroutine RSLT receives mileage results from PC*MILER. The subroutine PLOT can be used to send graphics requests for ETA truck display of graphics. For example, a truck or vehicle ID's Lat/Long, ZIP, or city name position can be sent to the PC using PLOT and the "DT" request. Then a "DR" request with the truck's origin and destination can be sent so that a graphical ETA can be determined. The data structures of these subroutines are described below.

The PC Mileage Server can respond to a total of thirteen types of mileage and graphic requests:

Mileage:

- VN** = Version of PC*MILER Highway Data being used by the server
- VA** = Validation that a stop (City, ZIP code, etc.) is recognized by PC*MILER or a list of possible matches to a partial city or ZIP code
- MI** = Total mileage for up to 30 stops
- SM** = Total mileage for up to 30 stops broken down by state or province
- HS** = Turn-by-turn driving instructions for up to 30 stops
- LL** = Returns the lat/long coordinates for a city or address (PC*MILER|Streets only)

Graphics:

- DR** = Draw Route for up to 30 Stops
- DT** = Draw up to 30 truck bitmaps or "push pins" on the map
- CT** = Clear Truck bitmap from a specified location
- CR** = Clear a drawn route line
- CA** = Clear all routes and trucks
- PR** = Print route
- PA** = Print all

The PC Mileage Server responds with the following types of returns:

- VR** – Version of PC*MILER or PC*MILER|Streets running on the PC
- PL** – Good/Bad Stop or a 'pick list' of potential matches
- CP** – Total Miles for a trip
- SR** – Total Miles for a trip broken down by state or province
- HR** – Turn-by-turn driving instructions or "highway segments"
- VN** returns a VR
- VA** returns a PL
- MI** returns a CP
- SM** returns a CP and an SR.
- HS** returns a CP, an SR and an HR
- LL** returns an LR

6.2 Request and Response Field Parameters

The following sections specify the field parameters for the request types defined in section 6.1 and the responses to each request type.

IMPORTANT NOTE: When using PC*MILER|Streets, the best matching for address location lookups can be accomplished using the guidelines stated below. These rules apply to batch or interactive integration. **It is recommended that a validation (VA) request always precede each mileage request, especially where street addresses are included,** in order to avoid misleading or incomplete output.

When you input a street address, use a city and state abbreviation whenever possible:

Example: **Princeton, NJ;1000 Herrontown Road** – The comma between the city and state is optional. The semicolon between the state abbreviation and the street address is required. Use a street number.

Example: **Princeton, NJ;1000 Herrontown Road** as opposed to “Princeton, NJ;Herrontown Road”. In this example, if Herrontown Road is 50 miles long and no address is included, the returned mileage could be very inaccurate.

When a street address is not supplied, do not send a semicolon:

Example: Send **08540** as opposed to “08540;” – a semicolon will cause the server to look up a blank address (unnecessary).

Three examples of correct input:

Trenton, NJ;21 Olden Avenue
New York, NY;118 Broadway
20001

6.2.1 Stop Validation (VA) Request and Response

The following are field parameters for stop and (for PC*MILER|Streets users) street address validation. A stop can be a city/state pair separated by a comma, a ZIP code, a latitude/longitude point or (with optional add-on modules) a Canadian Postal code or SPLC (Standard Position Location Codes). PC*MILER|Streets users may include street addresses.

For Cities with multiple ZIP codes, the first city in the returned list is the central city or default ZIP for that city, with the remaining ZIP codes returned in numeric order.

When generating potential matches for an address, PC*MILER|Streets does a "Grid Based" search. This means that the search area may extend beyond the city limits of the requested city for potential matches. You may receive back potential matches in a surrounding town. Pick lists are sorted in confidence order, with the "best" potential match returned first.

For example:

Requesting a pick list by setting REQ-CIT equal to Princeton,NJ;Linden* would return the following list:

08540 Princeton, NJ, Mercer; 1 Linden Lane
08540 Princeton, NJ, Mercer; 49 Linden Lane
08540 Princeton, NJ, Mercer; 80 Linden Lane
08540 Princeton, NJ, Mercer; 100 Linden Lane
08534 Pennington, NJ, Mercer; Linden & Woodmer
08534 Pennington, NJ, Mercer; Linden & Woodmer
08822 Flemington, NJ, Mercer; 1 Linden Court
08822 Flemington, NJ, Mercer; 1 Linden Court
08536 Plainsboro, NJ, Mercer; 2 Linden Lane
08536 Plainsboro, NJ, Mercer; 3 Linden Lane
08536 Plainsboro, NJ, Mercer; 4 Linden Lane

NOTE: Grid Based searches are only done with address level lookups (PC*MILER|Streets only).

Validation requests are important because error reporting in mileage requests is limited to the first two stops of a trip. If your bad stop is lower in the list of stops, you will not be told which is the non-valid stop; you will get a generic "Can't Run Trip" message. The VA request type can be used to produce lists of potential matches to partial spellings or ZIP codes.

Validation Request:

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	VA	Validate Stop or Address	
REQ-REF	10		Output Queue Name (ALK uses "Q" plus job number)	
Filler 6	6			
REGION (Worldwide Only)	1		Pos 19) A=Asia E=Europe, F=Africa N=North America O=Oceania S=South America	
Filler 1	1			
Force Pick List	1	P	Pos 21) P or Blank P=Force Pick List, or use wildcard * after a partial city or address	
Filler 7	7			
REQ-CIT	70		Pos 29) 70 bytes each left justified 38 byte maximum city name 1 byte comma (optional) 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or for PC*MILER Streets 1 byte semicolon ; followed by street address <u>Examples</u> Warminster,PA,BUCKS Warminster,PA;1174 NASSAU ROAD 18974 Lat/long format should be 1234567N,1234567W 5 digit zips only Canadian Postal Codes use the format L#L<space> #L# (add-on data module) For Standard Position Location Codes SPLC plus the number (add-on data module)	
Filler-CIT	630		blank	

Validation Response:

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	PL	Stop pick list	
REQ-REF	10		Output Queue Name	
Filler-3	3		3 blanks	
RESP-MORE	1		Pos 16) M = more data to follow	
Filler 2	2		2 blanks	
REGION	1		Pos 19) Echoed from Request	
Match	1		Pos 20)	
		L	List of Cities	
		Y	Exact match	
		N	No match	
Force Pick List			Pos 21) Echoed from Request P or Blank	
Filler-1	1		1 blanks	

RESP-Seq	4		Pos 23-26) Sequence for multiple responses
RESP-ERR	2		Pos 27-28 Error Code
		E2	Place not found
RESP-CIT	980		Array of 14 places 70 bytes each left justified or Error message if there is a problem
Filler	15		

6.2.2 Point-to-point Miles (MI) Request and Response

1. (Request) The following are field parameters for requesting miles. The purpose of the Mileage request is to allow the host application to retrieve point-to-point miles. This type of request could be used for a quick mile lookup from a host inquire program or for running several stop-off points in a batch environment. The host dispatching software could generate this request when a new trip is established.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	MI	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Trip Options	Positions 13-22		Request Position	
REQ-OPTION	1		Pos 1)	S=Shortest P=Practical N=State + National Network T=Toll Discouraged/Practical 5=State + National Network B=Toll Discouraged/Practical C=National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H=State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/ Shortest
	1		Pos 2)	M or K for miles or kilometers
	1		Pos 3)	R=resequence stops H=hub leg miles F=resequence stops fixed destination blank=otherwise
REQ-MORE	1		Pos 4)	M=more data to follow
	1		Pos 5)	Reserved by DR request
REQ-FMT	1		Pos 6)	E =Extended Format (Required, see Appendix A)

REGION (Worldwide Only)	1	Pos 7) A=Asia E=Europe, F=Africa N=North America O=Oceania S=South America
Custom Routing	1	Pos 8) C=Custom, blank=default
Override Restrictions	1	Pos 9) Y=Override Restrictions, L=Light N=Obey Restrictions or H=Heavy
Hazmat (Data Add-on)	1	Pos 10) G=General Restriction C=Corrosive E=Explosive Restriction F=Flammable I =Inhalant Restriction R = Radioactive Restriction
REQ-BRDR	1	Pos 11) O=Borders Open C= Closed
REQ-FERRY	1	Pos 12) Y=Include Ferry Distance N=Do Not Include Ferry Distance
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
REQ-CIT	700	Array of 10 places 70 bytes each left justified 3 sets of 700 when using the more flag 38 byte maximum city name 1 byte comma 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or 1 byte semicolon ; followed by street address

Examples
Warminster,PA,BUCKS
Warminster,PA;1174 NASSAU ROAD
18974
Lat/long format should be 1234567N,1234567W
5 digit zips only
Canadian Postal Codes use L#L<space> #L#
Standard Position Location Code use
SPLC+number

2. (Response) The following are field parameters for output miles. The City Pair response returns an output to the host application that contains city names and ZIP codes along with miles, cost and time estimates. The CP response is always returned first for all three request types (MI, SM, and HS).

Var Name	Len	Value	Description	<u>Extended Format</u>
RESP-TYPE	2	CP	City pair returned output	
RESP-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	

Request Options 13-22			
RESP-NET	1		Pos 1) S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National
Network/Practical			F=Toll Discouraged/ State + National Network
/Practical			G=Toll Discouraged/Shortest H=State + National Network/Shortest I= State + National Network /Shortest J=Toll Discouraged/State + National
Network/Shortest			K=Toll Discouraged/State + National
Network/Shortest			
RESP-MIL-TYPE	1	Pos 2)	M or K for miles or kilometers
RESP-OPTION	1	Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
RESP-MORE	1	Pos 4)	M = more data to follow
	1	Pos 5)	Reserved by DR request
REGION	1	Pos 6)	E=Extended Format
	1	Pos 7)	A=Asia, E=Europe, F=Africa, N=North America, O=Oceania, S=South America
Custom Routing	1	Pos 8)	C=Custom, blank=default
Override Restrictions	1	Pos 9)	Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10)	G=General Restriction C= Corrosive E=Explosive Restriction F=Flammable I =Inhalant Restriction R=Radioactive Restriction
RESP-SEQ	4		Sequence for multiple responses (Note: Border & Ferry settings not echoed in CP response.)
RESP-ERR	2		Error Code
		E1	First state not found
		E2	First city not found
		E3	Second state not found
		E4	Second city not found
		E5	Unable to resequence
		E6	Unable to calculate route
		E9	Disconnected Highway Network
RESP-CIT1	39		39 bytes All stop information including Zip and\or city\state and\or county and\or Street address or If there is error, the pcmiler error code

RESP-CIT2	39	39 bytes All stop information including Zip and\or city\state and\or county and\or Street address
RESP-MILE	5	Total miles returned or PC*MILER 3-digit error code
RESP-HOUR	4	Total time in hours (0031) = 3.1 hours
RESP-COST	7	Total cost for city pair (0052295) = 522.95
FILL133	133	
O256		Blank

6.2.3 State Miles (SM) Request and Response

1. (Request) The following are field parameters for a state miles request. The purpose of this request is to attain the state-by-state mileage information associated with a trip.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	SM	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Request Options 13-22				
REQ-OPTION	1		Pos 1) S=Shortest P=Practical N=State + National Network/Practical T=Toll Discouraged/Practical 5= State + National Network /Practical B=Toll Discouraged/Practical C=State + National Network/Practical D= State + National Network /Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/ State + National Network /Practical G=Toll Discouraged/Shortest H=State + National Network/Shortest I= State + National Network /Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/ State + National Network / Shortest	
	1		Pos 2) M or K for miles or kilometers	
	1		Pos 3) R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise	
REQ-MORE	1		Pos 4) M = more data to follow	
	1		Pos 5) Reserved by DR request	
REQ-FMT	1		Pos 6) E = Extended Format (Required, see Appendix A)	
REGION (Worldwide Only)	1		Pos 7) A=Asia E=Europe, F=Africa N=North America O=Oceania	

Custom Routing	1	S=South America
Override Restrictions	1	Pos 8) C=Custom, blank=default
		Pos 9) Y=Override Restrictions or L=Light
		N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10) G=General Restriction
		C=Corrosive
		E=Explosive Restriction
		F=Flammable
		I=Inhalant Restriction
		R=Radioactive Restriction
REQ-BRDR	1	Pos11) O=Borders Open C= Closed
REQ-FERRY	1	Pos12) Y=Include Ferry Distance N=Do Not Include
		Ferry Distance
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
REQ-CIT	700	Array of 10 places 70 bytes each left justified
		3 sets of 700 when using the more flag
		38 byte maximum city name
		1 byte comma
		2 byte state abbrev
		1 byte comma (optional)
		13 byte county name (optional)
		or
		1 byte semicolon ; followed by street address
		<u>Examples</u>
		Warminster,PA,BUCKS
		Warminster,PA;1174 NASSAU ROAD
		18974
		Lat/long format should be 1234567N,1234567W
		5 digit zips only
		Canadian Postal Codes use the format L#L #L#

2. (Response) The following are field parameters for the state miles output. The PC will respond with the miles (or kilometers) for the stops indicated in the "SM" request. There will be 10 state miles returned for each record. If additional records are needed, an "M" in the "MORE" parameters field is used to indicate that there is more data to follow.

NOTES: A "CP" (city pair, point-to-point miles) response is always returned first for all three request types (MI, SM, and HS), and an "SR" (state miles) output record follows the "CP" response to an "HS" (highway system, detailed route information) request (see section 6.2.4).

Response from PC	Len	Value	Description
REQTYPE	2	SR	State miles summary
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)
Request Options 13-22			
PARAMS	1	Pos 1)	S=Shortest P=Practical N=State + National/Practical

			T=Toll Discouraged/Practical 5= State + National Network /Practical B=Toll Discouraged/Practical C=State + National Network/Practical D= State + National Network /Practical E=Toll Discouraged/State + National
Network/Practical			F=Toll Discouraged/ State + National Network
/Practical			G=Toll Discouraged/Shortest H=State + National Network/Shortest I= State + National Network /Shortest J=Toll Discouraged/State + National
Network/Shortest			K=Toll Discouraged/ State + National Network / Shortest
	1	Pos 2)	M or K for miles or kilometers
	1	Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1	Pos 4)	M = more data to follow
	1	Pos 5)	Reserved by DR request
REQ-FMT	1	Pos 6)	E = Extended Format (Required, see Appendix A)
REGION	1	Pos 7)	A=Asia, E=Europe, F=Africa, N=North America, O=Oceania, S=South America
Custom Routing	1	Pos 8)	C=Custom, blank=default
Override Restrictions	1	Pos 9)	Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10)	G=General Restriction C=Corrosive E=Explosive Restriction F=Flammable I =Inhalant Restriction R=Radioactive Restriction
SEQNUM	4		Sequence for multiple responses (Note: Border & Ferry settings not echoed in CP response.)
ERROR	2		Error Code
		E1	First state not found
		E2	First city not found
		E3	Second state not found
		E4	Second city not found
		E5	Unable to resequence
		E6	Unable to calculate route
		E9	Disconnected Highway Network
STATEMIL	220		10 elements each element will consist of: 2 for state code 5 for total miles 4 for toll miles
FILLER	8		

6.2.4 Detailed Route Information (HS) Request and Response

1. (Request) Following are parameters for a route and state miles request. The purpose of this request is to allow the Host to retrieve detailed route information based on the city pair stop-off points.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	HS	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Request Options 13-22				
REQ-OPTION	1		Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5= State + National Network /Practical B=Toll Discouraged/Practical C=State + National Network/Practical D= State + National Network /Practical E=Toll Discouraged/State + National F=Toll Discouraged/ State + National Network G=Toll Discouraged/Shortest H=State + National Network/Shortest I= State + National Network /Shortest J=Toll Discouraged/State + National K=Toll Discouraged/ State + National Network /
Network/Practical				
/Practical				
Network/Shortest				
Shortest				
	1		Pos 2)	M or K for miles or kilometers
	1		Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1		Pos 4)	M = more data to follow
	1		Pos 5)	Reserved by DR request
REQ-FMT	1		Pos 6)	E = Extended Format (Required, see appendix A)
REGION	1		Pos 7)	A=Asia, E=Europe, F=Africa, N=North America, O=Oceania, S=South America
Custom Routing	1		Pos 8)	C=Custom, blank=default
Override Restrictions	1		Pos 9)	Y=Override Restrictions, L=Light N=Obey Restrictions or H=Heavy
Hazmat	1		Pos 10)	G=General Restriction C=Corrosive E=Explosive Restriction F=Flammable I=Inhalant Restriction R=Radioactive Restriction
REQ-BRDR	1		Pos11)	O=Borders Open C= Closed

REQ-FERRY	1	Pos12) Y=Include Ferry Distance N=Do Not Include Ferry Distance
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
REQ-CIT	700	Array of 10 places 70 bytes each left justified 3 sets of 700 when using the more flag 38 byte maximum city name 1 byte comma 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or 1 byte semicolon ; followed by street address

Examples
 Warminster,PA,BUCKS
 Warminster,PA;1174 NASSAU ROAD
 18974
 Lat/long format should be 1234567N,1234567W
 5 digit zips only
 Canadian Postal Codes use the formal L#L #L#

2. (Response) Following are field parameters for a response to the route and state miles request. The PC response record has all of the required detailed route information. There are four route list records\response records. Therefore, if there are more than four records for the route, additional response records must be returned. Multiple returned records are designated by the "M" in the "MORE" parameter field.

REMEMBER: A "CP" and "SR" output record will always precede the "HR" response record.

Response from PC	Len	Value	Description
REQTYPE	2	HR	Route highway information returned
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)
Request Options 13-22			
REQ-OPTION	1	Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5= State + National Network /Practical B=Toll Discouraged/Practical C=State + National Network/Practical D= State + National Network /Practical E=Toll Discouraged/State + National Network/Practical /Practical F=Toll Discouraged/ State + National Network G=Toll Discouraged/Shortest H=State + National Network/Shortest I= State + National Network /Shortest

		J=Toll Discouraged/State + National
Network/Shortest		K=Toll Discouraged/ State + National Network /Shortest
	1	Pos 2) M or K for miles or kilometers
	1	Pos 3) R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1	Pos 4) M = more data to follow
	1	Pos 5) Reserved by DR request
REQ-FMT	1	Pos 6) E = Extended Format (Required, see Appendix A)
REGION	1	Pos 7) A=Asia, E=Europe, F=Africa, N=North America, O=Oceania, S=South America
Custom Routing	1	Pos 8) C=Custom, blank=default
Override Restrictions	1	Pos 9) Y=Override Restrictions, L =Light, N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10) G=General Restriction C=Corrosive E=Explosive Restriction F=Flammable I=Inhalant Restriction R=Radioactive Restriction
SEQNUM	4	Sequence for multiple responses Note: Border & Ferry settings not echoed in CP response.
ERROR	2	Error code
		E1 First state not found
		E2 First city not found
		E3 Second state not found
		E4 Second city not found
		E5 Unable to resequence
		E9 Disconnected Highway Network
ROUTEINFO		2 indicates end of route data for stop
		2 state code
		1 toll indicator
	3 sets	6 directional (North, Turn L, etc)
		35 route number
		4 leg mileage
		38 for intersection city or junction
		6 for cumulative leg miles
		6 for cumulative stop miles

NOTES: The PC will send CP response records for MI requests.
 The PC will send CP and SR response records for SM requests.
 The PC will send CP, SR, and HR response records for HS requests


6.2.5 Upgrade Notice

For Version 16 and higher, the ROUTEINFO portion of the HS return was increased by 25 characters and the number of ROUTEINFO Sets per response packet was decreased from four sets to three. Route Number was increased 15 characters from 20 to 35 (Highway, Road or Street Name), and Interchange City or Junction was increased 10 characters from 28 to 38.

The previous format is shown below.

Format in previous versions:

ROUTEINFO



6.2.6 City/Address to Lat/Long Coordinates (LL) Request and Response

1. (Request) Following are parameters for latitude/longitude coordinates for a given city, postal code, or address (PC*MILER|Streets only). Lat/longs are returned in degree, minute second format.

For example:

0394346N,0861610W

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	LL	Lat/Long	
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)	
FILL-10	10		Blank Fill	
REQ-SEQ	4		Sequence (Always 0001 for LL Requests)	
REQ-ERR	2		Error Code	
REQ-CIT	70		38 byte maximum city name 1 byte comma or space 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or	

1 byte semicolon ; followed by street address

Examples

Warminster,PA,BUCKS

Warminster,PA;1174 NASSAU ROAD

18974

Lat/long format should be 1234567N,1234567W

5 digit zips only

Canadian Postal Codes use the formal L#L #L#

2. (Response) Following are parameters for a latitude longitude coordinate response. Lat/longs are returned in degree, minute second format.

For example:


0394346N,0861610W

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	LR	Lat/Long	
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)	
FILL-10	10		Blank Fill	
RESP-SEQ	4		Sequence (Always 0001 for LL Requests)	
RESP-ERR	2		Error Code (E2=No Match Found)	
RESP-LL	17		Lat/Long Coordinate in Degree, Minutes, Seconds Format	
Fill-211	211		Blank Fill	


6.3 Sample Request and Response Records

Sample records are shown below.

Sample State Miles (SM) request record:



Sample State Miles (SR) response record:



7.0 Using PC*MILER | Tolls with Other Transportation Software

Notes for Existing PC*MILER-AS400 Users:

- A set of 10 new trip parameters has been inserted into all of the request and response packets.
- All return types (CP, SR, HR) were expanded to hold Toll Cost information. CP was expanded by seven characters, SR by 77, and HR by 63.

For PC*MILER|Tolls, the ROUTEINFO portion of the HS return was increased by seven characters and the number of ROUTEINFO sets per response packet was increased from three to nine to improve performance. For users who are upgrading from Version 15 or less, see **NOTE** below for previous changes.

- Output Data Queue sizes were lengthened from 1024 to 1048.
- Data Area "TLLALK" (renamed from COMALK) was modified to store a default setting for toll cost requests.
- "Old mode" or short city names (22 characters) are not supported.

NOTE for Version 22-30: The following features are not supported in the AS400 product line: Fuel Optimization, Vehicle Profiles, Estimated Greenhouse Gas Emissions, RouteSync, TripDirect, Entry/Exit Toll Plaza Names in Reports, and Real-time/Historical Traffic Data. Province/Estado Abbreviation Option to set "NL" preference is supported in Version 25-30 only.

Added for Version 20 and higher: Borders Open/Closed and Use Ferry Distance options. The first two characters of the four-character "Request Sequence" have been re-mapped to hold the Borders and Ferry Flags.

Historically the Request Sequence values have been ignored by the PC Distance Server. Unlike other trip options, Border and Ferry settings are not echoed back in the responses from the PC.

For the optional **PC*MILER|HazMat** hazardous material routing package, two routing types have been added: **Caustic** and **Flammable**.

NOTE: PC*MILER 18 and higher now has full Mexican Estado information. Previously, all Mexican cities were referenced with 'MX' as the Estado code and the Estado was returned in the US county field. For example:

Older versions format: Mexico City, MX, Distrito Federal
Correct format for Version 18: Mexico City, DF

REMINDER: The Province/Estado Abbreviation Option to set the "NL" preference is supported only in Version 25-30.

Estados Codes:

AG	Aguascalientes
BJ	Baja California
BS	Baja California Sur
CP	Campeche
CH	Chiapas
CI	Chihuahua
CU	Coahuila de Zaragoza
CL	Colima
DF	Distrito Federal
DG	Durango
GJ	Guanajuato
GR	Guerrero
HG	Hidalgo
JA	Jalisco
EM	Mexico (Estado)
MH	Michoacan de Ocampo
MR	Morelos
NA	Nayarit
New for 25=> NX* or NL	Nuevo Leon (PC Side Configuration Option – Tools menu)
OA	Oaxaca
PU	Puebla
QA	Queretaro Arteaga
QR	Quintana Roo
SL	San Luis Potosi
SI	Sinaloa
SO	Sonora
TA	Tabasco
TM	Tamaulipas
TL	Tlaxcala
VZ	Veracruz
YC	Yucatan
ZT	Zacatecas

"NX" is used for Nuevo Leon because "NL" is already used in the database for the Canadian province of Newfoundland and Labrador. The option to configure NL for routing to Nuevo Leon is supported in Version 25-30 only.

NOTE: For Version 17 and higher the routing type options have changed for National Network, Toll Discouraged, and 53'/102" Trailer routing. These three routing options now can be generated in combination with the 'Practical' or 'Shortest' options. Additionally, National Network or 53' Trailer routing can be combined with the Toll Discouraged option. The only way to take advantage of this new functionality is to pass in the new code in position 1 of the Request Options.

NOTE: For V30 the 53 Foot Trailer routing option has been replaced with the 'State + National Network' routing option to better reflect the combination in previous versions of PC*MILER's National Network and 53 Foot Trailer Networks when the 53 Foot Trailer option was selected. For Third Party applications, ALK will continue to support the use of either the 'N' or '5' Network Types to turn on State + National Network Routing. The following extended routing types will also turn on State + National Routing portion of the request:

C = National Network/Practical

D = 53 Foot Trailer/Practical

E = Toll Discouraged/National Network/Practical

F = Toll Discouraged/53 Foot Trailer/Practical

H = National Network/Shortest

I = 53 Foot Trailer/Shortest

J = Toll Discouraged/National Network/Shortest

K = Toll Discouraged/53 Foot Trailer/Shortest

Previously the five available codes were:

P = Practical

S = Shortest

N = National Network

T = Toll Discouraged

5 = 53 Foot Trailer

New Codes:

P = Practical

S = Shortest

B = Toll Discouraged/Practical

C = National Network/Practical

- D** = 53 Foot Trailer/Practical
- E** = Toll Discouraged/National Network/Practical
- F** = Toll Discouraged/53 Foot Trailer/Practical
- G** = Toll Discouraged/Shortest
- H** = National Network/Shortest
- I** = 53 Foot Trailer/Shortest
- J** = Toll Discouraged/National Network/Shortest
- K** = Toll Discouraged/53 Foot Trailer/Shortest

Use of the old codes is still supported, no changes are required. Old codes for National Network (N), Toll Discouraged (T), and 53 Foot Trailer (5) will be generated using the Practical network. Changing this default to the Shortest network is not possible.

NOTE: For users upgrading from PC*MILER|Streets, the Light/Heavy vehicle option has been renamed to 'Override Restrictions'. Parameter codes have changed from L (Light) to Y (Override Restrictions) and H (Heavy) to N (Obey Restrictions). Use of L and H is still supported.

NOTE: For Version 16 and higher, the HS (Turn-by-Turn Driving Instructions) return packet was changed from previous versions. The fields for Route and Interchange were lengthened and the number of sets of route information was reduced from 4 sets per packet to 3. See section 7.2.4 for details.

REMINDER: *For Version 16 and higher you have the option of using a comma or a space between the city and state or province abbreviation.*

7.1 Technical Overview

The PC*MILER for the AS400 system uses distributed processing techniques (i.e. the processing is split into two). The user interface or interactive software is written in RPG and runs on the AS400. Small CL programs are used for the creation and removal of temporary data queues (output or response queues). The mileage calculation software is written in C++ and runs on a PC in the Windows environment.

The RPG programs communicate with the PC mileage calculation software through Client Access Express. The interactive software on the AS400 allows multiple users to look up point-to-point mileages and routes for up to thirty stop-off points. The Windows server application creates a data queue on the AS400 at startup called MIDQUE. The server application waits for mileage requests and processes them when received. While the server application is waiting for work to do, the PC can be used for other tasks such as PC*MILER graphics or terminal emulation.

AS400 Programs *(see Appendix I for information on renamed objects)*

Files	Description
TOLLINQ	Main AS400 inquiry program that sends request to MIDQUE data queue
TOLLINQC	CL program that creates output queue and starts TOLLINQ rpg.
CITLL	RPG program that verifies city ZIP spelling
CRTQ	CL program that creates an output data queue based on the job number
DELQ	CL program that deletes the queue created by CRTQ
GTTLAT	Sample RPG Program that converts City, Jurisdiction pairs or zip codes to Lat/longs
GTTLATC	CL program that creates output queue and starts GETLAT RPG
GTTMIL	Sample RPG Program that performs point-to-point mileage lookups
GTTMILC	CL program that creates output queue and starts GETMIL RPG
GTQNAMTL	RPG Program that determines library and data queue name for sending requests
VTLADR	RPG Program that validates ZIP codes, place names, and street addresses; also provides pick lists of ZIPs codes, names and addresses when partial name, ZIP or address is passed in RPG parameters.
MIDQUE	Data queue that contains input mileage lookup records
QUEUE	CL program that writes to the MIDQUE request data queue
TLSEND	External data structure for sending mileage requests
TLRESP	External data structure for receiving mileage output
TLDRW	External data structure for sending graphics requests to PC
TLSEND2	External data structure with field mappings for Borders and Use Ferry Distance

The program **TOLLINQ** contains two subroutines that can be used to integrate miles with other transportation software. The subroutine **SNDREQ** sends mileage requests to PC*MILER and the subroutine **RSLT** receives mileage results from PC*MILER. The subroutine **PLOT** can be used to send graphics requests for ETA truck display of graphics.

For example, a truck or vehicle ID's Lat/Long, ZIP, or city name position can be sent to the PC using **PLOT** and the "DT" request. Then a "DR" request with the truck's origin and destination can be sent so that a graphical ETA can be determined. The data structures of these subroutines are described below.

The PC Mileage Server can respond to a total of thirteen types of mileage and graphic requests:

Mileage:

- VN** = Version of PC*MILER being used by the server
- VA** = Validation that a stop (City, ZIP code, etc.) is recognized by PC*MILER or a list of possible matches to a partial city or ZIP code
- MI** = Total mileage for up to 30 stops
- SM** = Total mileage for up to 30 stops broken down by state or province
- HS** = Turn-by-turn driving instructions for up to 30 stops
- LL** = Returns the lat/long coordinates for a city or address (PC*MILER|Streets only)

Graphics:

- DR** = Draw Route for up to 30 Stops
- DT** = Draw up to 30 truck bitmaps or "push pins" on the map
- CT** = Clear Truck bitmap from a specified location
- CR** = Clear a drawn route line
- CA** = Clear all routes and trucks
- PR** = Print route
- PA** = Print all

The PC Mileage Server responds with the following types of returns:

- VR** – Version of PC*MILER running on the PC
- PL** – Good/Bad Stop or a 'pick list' of potential matches
- CP** – Total Miles for a trip
- SR** – Total Miles for a trip broken down by state or province
- HR** – Turn-by-turn driving instructions or "highway segments"
- VN** returns a VR
- VA** returns a PL
- MI** returns a CP
- SM** returns a CP and an SR.
- HS** returns a CP, an SR and an HR
- LL** returns an LR

7.2 Request and Response Field Parameters

The following sections specify the field parameters for the request types defined in section 7.1 and the responses to each request type.

IMPORTANT NOTE: When using PC*MILER|Streets, the best matching for address location lookups can be accomplished using the guidelines stated below. These rules apply to batch or interactive integration. **It is recommended that a validation (VA) request always precede each mileage request, especially where street addresses are included,** in order to avoid misleading or incomplete output.

When you input a street address, use a city and state abbreviation whenever possible:

Example: **Princeton, NJ;1000 Herrontown Road** – The comma between the city and state is optional. The semicolon between the state abbreviation and the street address is required. Use a street number.

Example: **Princeton, NJ;1000 Herrontown Road** as opposed to “Princeton, NJ;Herrontown Road”. In this example, if Herrontown Road is 50 miles long and no address is included, the returned mileages could be very inaccurate.

When a street address is not supplied, do not send a semicolon:

Example: Send **08540** as opposed to “08540;” – a semicolon will cause the server to look up a blank address (unnecessary).

Three examples of correct input:

Trenton, NJ;21 Olden Avenue
New York, NY;118 Broadway
20001

7.2.1 Stop Validation (VA) Request and Response

The following are field parameters for stop and (for PC*MILER|Streets users) street address validation. A stop can be a city/state pair separated by a comma, a ZIP code, a latitude/longitude point, or (with optional add-on modules) a Canadian Postal Code or SPLC (Standard Position Location Codes). PC*MILER|Streets users may include street addresses.

For cities with multiple ZIP codes, the first city in the returned list is the central city or default ZIP for that city, with the remaining ZIP codes returned in numeric order.

When generating potential matches for an address, PC*MILER|Streets does a "Grid Based" search. This means that the search area may extend beyond the city limits of the requested city for potential matches. You may receive back potential matches in a surrounding town. Pick lists are sorted in confidence order, with the "best" potential match returned first.

For example:

Requesting a pick list by setting REQ-CIT equal to Princeton,NJ;Linden* would return the following list:

08540 Princeton, NJ, Mercer; 1 Linden Lane
08540 Princeton, NJ, Mercer; 49 Linden Lane
08540 Princeton, NJ, Mercer; 80 Linden Lane
08540 Princeton, NJ, Mercer; 100 Linden Lane
08534 Pennington, NJ, Mercer; Linden & Woodmer
08534 Pennington, NJ, Mercer; Linden & Woodmer
08822 Flemington, NJ, Mercer; 1 Linden Court
08822 Flemington, NJ, Mercer; 1 Linden Court
08536 Plainsboro, NJ, Mercer; 2 Linden Lane
08536 Plainsboro, NJ, Mercer; 3 Linden Lane
08536 Plainsboro, NJ, Mercer; 4 Linden Lane

NOTE: Grid Based searches are only done with address level lookups (PC*MILER|Streets only).

Validation requests are important because error reporting in mileage requests is limited to the first two stops of a trip. If your bad stop is lower in the list of stops, you will not be told which is the non-valid stop, you will get a generic "Can't Run Trip" message. The VA request type can be used to produce lists of potential matches to partial spellings or ZIP codes.

For PC*MILER|Tolls, the VA Request layouts and the PL Response layouts were increased by 10 characters to hold a new set of trip parameters. Output data queues increased from 1024 to 1048.

Validation Request:

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	VA	Validate Stop or Address	
REQ-REF	10		Output Queue Name (ALK uses "Q" plus job number)	
Filler-8	8			
Force Pick List	1	P	Pos 21) P or Blank P=Force Pick List, or use wildcard *	after a partial city or address
Filler-17	17		Pos 22-38) blanks, previously 7 characters.	
REQ-CIT	70		Pos 39) 70 bytes each left justified 38 byte maximum city name 1 byte comma (or optional space) 2 byte state abbrev 1 byte comma (or optional space) 13 byte county name (optional) or for PC*MILER Streets 1 byte semicolon ; followed by street address	
			<u>Examples</u> Warminster,PA,BUCKS Warminster,PA;1174 NASSAU ROAD 18974 Lat/long format should be 1234567N,1234567W 5 digit zips only Canadian Postal Codes use the format L#L<space> #L# (add-on data module) For Standard Position Location Codes SPLC plus the number (add-on data module)	

Validation Response:

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	PL	Stop pick list	
REQ-REF	10		Output Queue Name	
Filler-3	3		3 blanks	
RESP-MORE	1		Pos 16) M = more data to follow	
Filler-3	3			
Match	1		Pos 20)	
		L	List of Cities	
		Y	Exact match	
		N	No match	
Force Pick List			Pos 21) Echoed from Request P or Blank	
Filler-1	1		1 blank	
RESP-Seq	4		Pos 23-26) Sequence for multiple responses	
RESP-ERR	2		Pos 27-28 Error Code	
		E2	Place not found	
Filler 10	10		Pos 29-38)	
RESP-CIT	980		Pos 39-1018) Array of 15 places, 70 bytes each left justified or Error message if there is a problem	
Filler-16	16		Pos 1019-1035	
Total	1035			

7.2.2 Point-to-point Miles (MI) Request and Response

For PC*MILER|Tolls, the MI Request layout was increased by 10 to hold a new set of trip parameters. The CP Response layout was increased by these 10 new trip parameters plus 7 characters to hold Tolls Cost data. Output data queues increased from 1024 to 1048.

1. (Request) The following are field parameters for requesting miles. The purpose of the Mileage request is to allow the host application to retrieve point-to-point miles. This type of request could be used for a quick mileage lookup from a host inquire program or for running several stop-off points in a batch environment. The host dispatching software could generate this request when a new trip is established.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	MI	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Trip Options Positions	13-22		Request Position	
REQ-OPTION	1		Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H= State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest
	1		Pos 2)	M or K for miles or kilometers
	1		Pos 3)	R=resequence stops H=hub leg miles F=resequence stops fixed destination blank=otherwise
REQ-MORE	1		Pos 4)	M=more data to follow
	1		Pos 5)	Reserved by DR request
REQ-FMT	1		Pos 6)	E =Extended Format (Required, see Appendix A)
REGION (Worldwide Only)	1		Pos 7)	A=Asia E=Europe, F=Africa N=North America O=Oceania S=South America

Custom Routing	1	Pos 8) C=Custom, blank=default
Override Restrictions	1	Pos 9) Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat (Data Add-on)	1	Pos 10) G = General Restriction C=Corrosive E=Explosive Restriction F=Flammable I=Inhalant Restriction R=Radioactive Restriction
REQ-BRDR	1	Pos11) O=Borders Open C= Closed
REQ-FERRY	1	Pos12) Y=Include Ferry Distance N=Do Not Include Ferry Distance
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
More Trip Options		Pos 29-38)
REQ-MVS	3	Pos 1-3) MVS Version Only*
REQ-TollCost 1		Pos 4) T for Cash D for Discount or Blank
REQ—Fill 6		Pos 5-10) Not used blank fill
REQ-CIT	700	Array of 10 places 70 bytes each left justified 3 sets of 700 when using the more flag 38 byte maximum city name 1 byte comma (or optional space) 2 byte state abbrev 1 byte comma (or optional space) 13 byte county name (optional) or 1 byte semicolon ; followed by street address <u>Examples</u> Warminster,PA,BUCKS Warminster,PA;1174 NASSAU ROAD 18974 Lat/long format should be 1234567N,1234567W 5 digit zips only Canadian Postal Codes use L#L<space> #L# Standard Position Location Code use SPLC+number

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

2. (Response) The following are field parameters for output miles. The City Pair response returns an output to the host application that contains city names and ZIP codes along with miles, cost and time estimates. The CP response is always returned first for all three request types (MI, SM, and HS).

Var Name	Len	Value	Description	Extended Format
RESP-TYPE	2	CP	City pair returned output	
RESP-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Request Options	13-22			
RESP-NET	1		Pos 1) S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H=State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest	
RESP-MIL-TYPE	1		Pos 2) M or K for miles or kilometers	
RESP-OPTION	1		Pos 3) R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise	
RESP-MORE	1		Pos 4) M = more data to follow Pos 5) Reserved by DR request	
REGION	1		Pos 6) E=Extended Format Pos 7) A=Asia,E=Europe,F=Africa,N=North America,O=Oceania,S=South America	
Custom Routing	1		Pos 8) C=Custom, blank=default	
Override Restrictions	1		Pos 9) Y=Override Restrictions or L=Light N=Obey Restrictions or H=Heavy	
Hazmat	1		Pos 10) G = General Restriction C=Corrosive E = Explosive Restriction F=Flammable I = Inhalant Restriction R = Radioactive Restriction	
RESP-SEQ	4		Sequence for multiple responses (Note: Border & Ferry settings not echoed in CP response.)	
RESP-ERR	2		Error Code	
		E1	First state not found	
		E2	First city not found	
		E3	Second state not found	
		E4	Second city not found	
		E5	Unable to resequence	
		E6	Unable to calculate route	

		E9	Disconnected Highway Network (Echoed Back From Request)
More Options	29 -38		Pos 1-3) MVS Version Only*
RESP-MVS	3		Pos 4) Tolls Cost
RESP-TollCost	1		Post 5-10) Not Used
RESP-FILL	6		39 bytes
RESP-CIT1	39		All stop information including Zip and\or city\state and\or county and\or Street address or If there is error, the error code
RESP-CIT2	39		39 bytes All stop information including Zip and\or city\state and\or county and\or Street address
RESP-MILE	5		Total miles returned or 3-digit error code
RESP-HOUR	4		Total time in hours (0031) = 3.1 hours
RESP-COST	7		Total cost for city pair (0052295) = 522.95
RESP-TollCost	7		Tolls Cost for city pair (0007920) = \$79.20
FILL127	127		Blanks
Total	267		

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

7.2.3 State Miles (SM) Request and Response

For PC*MILER|Tolls, the SM Request layouts were increased by 10 to hold a new set of Trip Parameters. The SR Response Layouts were increased by these 10 new trip parameters plus 70 characters (10 sets of 7) to hold Tolls Cost data. Output Data Queues increased from 1024 to 1048.

1. (Request) The following are field parameters for a state miles request. The purpose of this request is to attain the state-by-state mileage information associated with a trip.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	SM	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Request Options 13-22				
REQ-OPTION	1		Pos 1) S=Shortest P=Practical	N=State + T=Toll Discouraged/Practical
National/Practical				

		5=State + National Network/Practical
		B=Toll Discouraged/Practical
		C=State + National Network/Practical
		D=State + National Network/Practical
		E=Toll Discouraged/State + National Network/Practical
		F=Toll Discouraged/State + National Network/Practical
		G=Toll Discouraged/Shortest
		H=State + National Network/Shortest
		I=State + National Network/Shortest
		J=Toll Discouraged/State + National Network/Shortest
		K=Toll Discouraged/State + National Network/Shortest
	1	Pos 2) M or K for miles or kilometers
	1	Pos 3) R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1	Pos 4) M = more data to follow
	1	Pos 5) Reserved by DR request
REQ-FMT	1	Pos 6) E = Extended Format (Required, see Appendix A)
REGION (Worldwide Only)	1	Pos 7) A=Asia E=Europe, F=Africa N=North America O=Oceania S=South America
Custom Routing	1	Pos 8) C=Custom, blank=default
Override Restrictions	1	Pos 9) Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10) G = General Restriction C=Corrosive E = Explosive Restriction F=Flammable I = Inhalant Restriction R = Radioactive Restriction
REQ-BRDR	1	Pos11) O=Borders Open C= Closed
REQ-FERRY	1	Pos12) Y=Include Ferry Distance N=Do Not Include Ferry Distance
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
More Trip Options	10	Pos 29-38)
REQ-MVS	3	Pos 1-3) MVS Version Only*
REQ-TollCost	1	Pos 4) T for Cash D for Discount or Blank
REQ—Fill 6		Pos 5-10) Not used blank fill
REQ-CIT	700	Array of 10 places 70 bytes each left justified 3 sets of 700 when using the more flag 38 byte maximum city name 1 byte comma 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or 1 byte semicolon ; followed by street address <u>Examples</u>

Warminster,PA,BUCKS
 Warminster,PA;1174 NASSAU ROAD
 18974
 Lat/long format should be 1234567N,1234567W
 5 digit zips only
 Canadian Postal Codes use the format L#L #L#

NOTE: REQ-SEQ is not read for SM requests.
 REQ-BRDR and REQ-FERRY values are not echoed back in the PC responses.

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

2. (Response) The following are field parameters for the state miles output. The PC will respond with the miles (or kilometers) for the stops indicated in the "SM" request. There will be 10 state miles returned for each record. If additional records are needed, an "M" in the "MORE" parameters field is used to indicate that there is more data to follow.

NOTES: A "CP" (city pair, point-to-point miles) response is always returned first for all three request types (MI, SM, and HS), and an "SR" (state miles) output record follows the "CP" response to an "HS" (highway system, detailed route information) request (see section 7.2.4).

Response from PC	Len	Value	Description
REQTYPE	2	SR	State miles summary
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)
Request Options 13-22			
PARAMS	1	Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H=State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest
	1	Pos 2)	M or K for miles or kilometers
	1	Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1	Pos 4)	M = more data to follow
	1	Pos 5)	Reserved by DR request

REQ-FMT	1		Pos 6) E = Extended Format (Required, see Appendix A)
REGION	1		Pos 7) A=Asia,E=Europe,F=Africa,N=North America,O=Oceania,S=South America
Custom Routing	1		Pos 8) C=Custom, blank=default
Override Restrictions	1		Pos 9) Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat	1		Pos 10) G = General Restriction C=Corrosive E = Explosive Restriction F=Flammable I = Inhalant Restriction R = Radioactive Restriction
SEQNUM	4		Sequence for multiple responses (Note: Border & Ferry settings not echoed in CP response.)
ERROR	2		Error Code
		E1	First state not found
		E2	First city not found
		E3	Second state not found
		E4	Second city not found
		E5	Unable to resequence
		E6	Unable to calculate route
		E9	Disconnected Highway Network (Echoed Back From Request)
More Options 29 -38			
RESP-MVS	3		Pos 1-3) MVS Version Only
RESP-TollCost	1		Pos 4) Tolls Cost
RESP-FILL	6		Post 5-10) Not Used
STATEMIL	180		10 elements, each element will consist of:
		10 Sets	2 for state code
			5 for total miles
			4 for toll miles
			7 for Tolls Costs
FILLER	48		Blanks
Total 267			

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

7.2.4 Detailed Route Information (HS) Request and Response

For PC*MILER|Tolls, the HS Request layouts were increased by 10 to hold a new set of Trip Parameters. The HR Response Layouts were changed in two ways: The number of Sets of Route Information was increased from three to nine to improve performance. This route information was increased by 63 to hold Tolls Cost data (7 x 9 sets). Output Data Queues increased from 1024 to 1048.

1. (Request) Following are parameters for a route and state miles request. The purpose of this request is to allow the Host to retrieve detailed route information based on the city pair stop-off points.

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	HS	Miles request	
REQ-REF	10		Output Queue Name (ALK uses 'Q' + the job number)	
Request Options 13-22				
REQ-OPTION	1		Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H=State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest
	1		Pos 2)	M or K for miles or kilometers
	1		Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1		Pos 4)	M = more data to follow
	1		Pos 5)	Reserved by DR request
REQ-FMT	1		Pos 6)	E = Extended Format (Required see appendix A)
REGION	1		Pos 7)	A=Asia, E=Europe, F=Africa, N=North America, O=Oceania, S=South America
Custom Routing	1		Pos 8)	C=Custom, blank=default
Override Restrictions	1		Pos 9)	Y=Override Restrictions or L=Light N=Obey Restrictions or H=Heavy

Hazmat	1	Pos 10) G = General Restriction C=Corrosive E = Explosive Restriction F=Flammable I = Inhalant Restriction R = Radioactive Restriction
REQ-BRDR	1	Pos11) O=Borders Open C= Closed (not echoed back)
REQ-FERRY	1	Pos12) Y=Include Ferry Distance N=Do Not Include Ferry Distance (not echoed back)
REQ-SEQ	2	Sequence for multiple responses (Not read by PC)
REQ-ERR	2	Error Code
More Trip Options	10	Positions 29-38)
REQ-MVS	3	Pos 1-3) MVS Version Only*
REQ-TollCost	1	Pos 4) T for Cash D for Discount or Blank
REQ—Fill 6		Pos 5-10) Not used blank fill
REQ-CIT	700	Array of 10 places 70 bytes each left justified 3 sets of 700 when using the more flag 38 byte maximum city name 1 byte comma (or space) 2 byte state abbrev 1 byte comma (or space) 13 byte county name (optional) or 1 byte semicolon ; followed by street address <u>Examples</u> Warminster,PA,BUCKS Warminster,PA;1174 NASSAU ROAD 18974 Lat/long format should be 1234567N,1234567W 5 digit zips only Canadian Postal Codes use the formal L#L #L#

NOTE: REQ-SEQ is not read for HS requests.
REQ-BRDR and REQ-FERRY values are not echoed back in the PC responses.

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

2. (Response) Following are field parameters for a response to the route and state miles request. The PC response record has all of the required detailed route information. There are four route list records\response records. Therefore, if there are more than nine records for the route, additional response records must be returned. Multiple returned records are designated by the "M" in the "MORE" parameter field.

REMEMBER: A "CP" and "SR" output record will always precede the "HR" response record.

Response from PC	Len	Value	Description
REQTYPE	2	HR	Route highway information returned
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)
Request Options	13-22		
REQ-OPTION	1	Pos 1)	S=Shortest P=Practical N=State + National/Practical T=Toll Discouraged/Practical 5=State + National Network/Practical B=Toll Discouraged/Practical C=State + National Network/Practical D=State + National Network/Practical E=Toll Discouraged/State + National Network/Practical F=Toll Discouraged/State + National Network/Practical G=Toll Discouraged/Shortest H= State + National Network/Shortest I=State + National Network/Shortest J=Toll Discouraged/State + National Network/Shortest K=Toll Discouraged/State + National Network/Shortest
	1	Pos 2)	M or K for miles or kilometers
	1	Pos 3)	R = resequence stops H = hub leg miles F = resequence stops fixed destination blank = otherwise
REQ-MORE	1	Pos 4)	M = more data to follow
	1	Pos 5)	Reserved by DR request
REQ-FMT	1	Pos 6)	E = Extended Format (Required see appendix A)
REGION	1	Pos 7)	A=Asia,E=Europe,F=Africa,N=North America,O=Oceania,S=South America
Custom Routing	1	Pos 8)	C=Custom, blank=default
Override Restrictions	1	Pos 9)	Y=Override Restrictions, L=Light, N=Obey Restrictions or H=Heavy
Hazmat	1	Pos 10)	G = General Restriction C=Corrosive E = Explosive Restriction F = Flammable I = Inhalant Restriction R = Radioactive Restriction
SEQNUM	4		Sequence for multiple responses
ERROR	2		Error code


- E1 First state not found
- E2 First city not found
- E3 Second state not found
- E4 Second city not found
- E5 Unable to resequence
- E9 Disconnected Highway Network
- E9 Disconnected Highway Network

More Options 29 -38

RESP-MVS	3	(Echoed Back From Request)
RESP-TollCost	1	Pos 1-3) MVS Version Only*
RESP-FILL	6	Pos 4) Tolls Cost
		Post 5-10) Not Used

Number of Sets increased from 3 to 9, 7 characters added to each set to hold Tolls Cost Data

ROUTEINFO



Fill-34 34

Total 1035

- NOTES:**
- The PC will send CP response records for MI requests.
 - The PC will send CP and SR response records for SM requests.
 - The PC will send CP, SR, and HR response records for HS requests

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.


7.2.5 Upgrade Notice

For Version 16 and higher the ROUTEINFO portion of the HS return was increased by 25 characters and the number of ROUTEINFO Sets per response packet was decreased from four sets to three. Route Number was increased 15 characters from 20 to 35 (Highway, Road or Street Name), and Interchange City or Junction was increased 10 characters from 28 to 38.

The previous format is shown below.


Format in previous non-tolls versions:

ROUTEINFO



Format in PC*MILER|Tolls versions:

ROUTEINFO



7.2.6 City/Address to Lat/Long (LL) Request and Response

1. (Request) Following are parameters for latitude/longitude coordinates for a given city, postal code, or address (PC*MILER|Streets only). Lat/longs are returned in degree, minute second format.

For example:

0394346N,0861610W

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	LL	Lat/Long	
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)	
FILL-10	10		Blank Fill	
REQ-SEQ	4		Sequence (Always 0001 for LL Requests)	
REQ-ERR	2		Error Code	
More Trip Options	10		Positions 29-38)	
REQ-MVS	3		Pos 1-3) MVS Version Only	
REQ-TollCost	1		Pos 4) Not Used LL Request Type	
REQ—Fill 6			Pos 5-10) Not used blank fill	
REQ-CIT	70		38 byte maximum city name 1 byte comma or space 2 byte state abbrev 1 byte comma (optional) 13 byte county name (optional) or 1 byte semicolon ; followed by street address	
			<u>Examples</u> Warminster,PA,BUCKS Warminster,PA;1174 NASSAU ROAD 18974 Lat/long format should be 1234567N,1234567W 5 digit zips only Canadian Postal Codes use the formal L#L #L#	

1. (Response) Following are parameters for a latitude longitude coordinate response. Lat/longs are returned in degree, minute second format.

For example:

0394346N,0861610W

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	LR	Lat/Long	
REFNUM	10		Output Queue Name (ALK uses 'Q' + the job number)	

FILL-10	10	Blank Fill
RESP-SEQ	4	Sequence (Always 0001 for LL Requests)
RESP-ERR	2	Error Code (E2=No Match Found)
More Options	29 -38	(Echoed Back From Request)
RESP-MVS	3	Pos 1-3) MVS Version Only*
RESP-TollCost	1	Pos 4) Not Used LL Requests
RESP-FILL	6	Post 5-10) Not Used
RESP-LL	17	Lat/Long Coordinate in Degree, Minutes, Seconds Format
Fill-211	211	Blank Fill

* "MVS" is the PC*MILER Multi Version Switch product, an optional product that allows for connection to multiple versions of PC*MILER.

7.2.7 Optional: PC Server Version (VN) Request and Response

Used to check the version of PC*MILER software running on the Server PC.

Version Request:

Var Name	Len	Value	Description	<u>Extended Format</u>
REQ-TYPE	2	VN	Version of PC Software Running	
REQ-REF	10		Output Queue Name (ALK uses "Q" plus job number)	


Version Response:

Var Name	Len	Value	Description	<u>Extended Format</u>
RESP-TYPE	2	VR	Stop pick list	
RESP-REF	10		Output Queue Name	
Filler- 26	26		Pos 13) blanks	
RESP-Ver	20		Pos 39) Version/Type PC Software	
Filler-209	209		Pos 59) blanks	
Total = 267				


7.2.8 Sample Request and Response Records

Sample records are shown below.

Sample State Miles (SM) request record:



Sample State Miles (SR) response record:



8.0 Menus

All menu commands in PC*MILER for the AS400 are described on the following pages.

The File Menu

Using the **File** menu, you can open, close, save and duplicate routes; print graphics and reports; and exit the PC*MILER program.

Delete AS400 Input Queue	When a queue becomes corrupted, creates a new queue and deletes the corrupted one.
Exit	Exit PC*MILER-AS400. When you exit, all active windows are saved as they appear on your screen for the next time PC*MILER-AS400 is opened.
AS400 Control	<p>Configure the Mileage server for different purposes. Choose from the sub-menu:</p> <p>Change Library/Queue: Location of request/input queue. Default Library is ALKWIN or ALKTLL for PC*MILER Tolls. Default Data Queue Name is MIDQUE. Innovative users, use your ICC work library, i.e. ITRS6WORK or IESR7WORK. If you want to display routes/trucks for requests coming from this one PC rather than for all requests, use your AS400 display name instead of MIDQUE.</p> <p>Mapping on: Turn mapping on or off. Turning off mapping can speed up batch applications.</p>

	<p>Graphics for Mile Requests: Turn mapping on or off. The routes will not be drawn on the map. This will speed up the display.</p> <p>Log to File: Turn diagnostics on/off. This is useful for debugging problems. When on, diagnostics are written to a file called as400.log, located in the directory that the software is running from (srv32.exe). Choose between Append, Overwrite, and Close.</p> <p>Host Polling Timer: Use faster time slice to poll the AS400 more often for faster interactive response time, or slower time slice for smoother graphic display.</p> <p>Force Pick List: Turns AS400 pick lists off/on for duplicate city names. Activates lists for both large cities with multiple ZIP codes and duplicate city names.</p>
--	--

The Window Menu

Use the **Window** menu to control and organize the active windows in your display.

Tile Vertical	Active windows will fit your screen, running vertically.
Tile Horizontal	Active windows will fit your screen, running horizontally.
Display Serve Log	Restore the Serve Log window if minimized.

9.0 Common Questions and Installation Problems

Question: *PC*MILER works correctly when using the PCMILER command on the AS400, but my Innovative software does not work.*

Answer: Run the CONFIG command on the AS400 (which is described in the manual) and type the Innovative work library name **I93WORK**, **ITSR5W0RK**, or **IESR7WORK** (check with ICC). After this is complete, check the File menu in the AS400 Mileage Server, **choose AS400 Control>Change Library Queue**. Or you can edit the PCMSERVE.INI or PMWSSRV.INI for PC*MILER|Streets, changing the LIBRARY=ALKWIN to LIBRARY=I93WORK and then restart the AS400 Mileage Server. Or re-install the AS400 windows CD and type **I93WORK**. Restart the SERVER.

Question: *The Interactive PC*MILER screen crashes when I type in an ICC Short City Code.*

Answer: PC*MILER does a lookup in an ICC Cities database when you use Short City Codes, a component program of PC*MILER needs to be compiled with access to your Cities database. The compile will fail unless you have ALKWIN and your Innovative work and file libraries in your library list. Get a 400 command line and do a DSPLIB, make sure you have ALKWIN and your two Innovative Libraries in your list. The Innovative libraries are different from release to release. They can be I93WORK and I93DATA, or ITSR4WORK and ITSR4FILE, or ITSR5WORK and ITSR5FILE, or ITSR6WORK and ITSR6FILE, or IESR7WORK and IESR7FILE. If the necessary libraries are not in your list use the ADDLIBLE command to add them. Then do a WRKOBJPDM<space>ALKWIN. Do a 12 on QRPGRSRC and then a 14 on CITICC, say yes to replace existing member.

Question: *PC*MILER works correctly but my Innovative Print Missing Tariff miles is not returning miles for a few cities.*

Answer: The city spellings in the Innovative city file are different than in PC*MILER. Use the report from the Print Missing Tariff Miles (which lists the city discrepancies) and type **PCMILER** from the AS400 command line. Now type the city code in, e.g. **OCOK** (should be Oklahoma City OK) and press **<ENTER>**. PC*MILER will indicate that it is not found. Now use the long

spelling of the city, for example **ok* OK**, to determine the PC*MILER spelling. Press **<F16>** to invoke the ICC city update program and correct the spelling for Oklahoma City OK. After all the corrections are made, re-run the ICC Print Missing Tariff Miles utility to update those missing miles.

Question: *Some of the mileage returned from PC*MILER is different from the mileage returned by my other transportation software.*

Answer: The city spelling or ZIP being used by the other software is probably not correct. To verify what place name is being sent to PC*MILER, click on the Pick Pins icon and then on the stop-off point in the mapping window. Now correct your AS400 cities file.

Question: *When I change my queue name to "MIDQUE", my PC can't receive anything from the AS400.*

Answer: Make sure that you exit and restart the PC*MILER interactive software on the AS400. The PC*MILER program on the AS400 will detect the presence of the new queue and it will send requests to this queue.

Question: *The interactive response time has become slower on the AS400 since we have added several more users. Can we improve the performance?*

Answer: Yes. You can run multiple copies of the PC*MILER-AS400 program on the same PC if you have enough memory. Or if you have another available PC, you can start up PC*MILER-AS400 on the other PC.

Question: *How can I run PC*MILER-AS400 on more than one PC?*

Answer: Make sure that PC*MILER-AS400 is installed properly on each PC. Additionally, set the queue name to **MIDQUE** so that the multiple PC's are servicing the same queue.

10.0 Technical Support

Technical support is available to registered users of PC*MILER-AS400 from **8:00am** to **5:00pm EST, Monday through Friday**. Call **(609) 683-0220, ext. 2**. Or, e-mail us at **pcmsupport@alk.com** (type "PCM/AS400" in the subject line).

11.0 About ALK® Technologies

ALK® Technologies, Inc., a Trimble® company headquartered in Princeton, NJ, was founded in 1979 as a transportation industry pioneer. ALK harnesses the power of information technology to enhance transportation and mobility, supporting competitive advantage and improved quality of life.

Today, ALK is a global leader in GeoLogistics® solutions and navigation software, focused on developing innovative solutions for transportation, logistics, mobile workforces and consumers. Product lines include award-winning CoPilot®, a leading source of GPS navigation software for fleets, mobile operators, hardware OEMs, systems integrators, professional drivers and consumers. ALK's PC*MILER® is widely recognized as a transportation industry standard for routing, mileage and mapping. ALK® Maps is a development platform designed for the transportation industry and provides commercial routing, geocoding and mapping visualization for enterprise applications.

For detailed product information, visit us at
www.alk.com or www.pcmiler.com.



Appendix A: Backward Compatibility

ALK Technologies does support backward compatibility with previous versions of PC*MILER and PC*MILER for the AS400. However, it is **not** advisable to develop new applications that use these short city name structures, because you lose access to county information which is necessary for resolving duplicate city name problems. Over time, this backward compatibility becomes increasingly difficult for ALK Technologies to maintain. Future backward compatibility is not guaranteed.

If you would like more information about backward-compatible formats, please contact the ALK technical support staff (see Chapter 9).

Appendix B: Configuring an N/S Router For Use With PC*MILER-AS400

ALK is no longer supporting the use of the N/S Router. It remains an installation option and may work on some systems.

Unless you have a twinax connection, configure your router using the AnyNet protocol. AnyNet needs to be enabled on the AS400 (see *Appendix D: Configuring AnyNet on the AS400*).


For PC*MILER Version 14 (or higher) and any PC*MILER|Streets version, you must have the N/S Router version 3.0 or higher.



Check by selecting **HELP > About** in the NS/Administrator or the midrange workspace.


NOTE: If you need to upgrade your NS Router, you must reinstall the PC*MILER-AS400 interface afterwards. The PC*MILER interface is built on a specific Netsoft Data Queue DLL that is available only on the PC*MILER interfaces CD.

To start the configuration, go to the N/S Administrator, right click on the N/S Router, and choose Properties.




Then do the following:



1. In the Links Tab, highlight AnyNet, and then choose Properties.



2. In Properties, fill in the AS400's IP address. You can use a system name, but if your host tables are not filled in properly, you will be able to connect to the AS400, but PC*MILER won't be able to create a Data Queue.



- The Systems tab adds the AS400's system name. This is where you set the password with which the router signs in. Make sure that the password has not expired, and that the account has object authority to the library where your mileage request Data Queue will reside (usually **alkwin** or an Innovative Work Library).



4. In the local LU tab use the second option, **Use a local specific value.**

The screenshot shows a dialog box titled "Properties for NS/Router" with a blue header bar containing a help icon and a close button. Below the header are five tabs: "Links", "Systems", "Common", "Local LU", and "Options". The "Local LU" tab is selected. The main area of the dialog contains the text "This property page contains configuration data for Local LU." Below this is a "Net ID:" label followed by a text box containing ".APPN". Underneath is a "PC Location Name" label followed by a group box containing five radio button options, each with a corresponding text box: "Use a shared value:" (empty), "Use a local specific value:" (containing "MILESPC"), "Use log in name:" (empty), "Use computer name:" (empty), and "Use the default name in the SNA server:" (empty). The "Use a local specific value:" option is selected. At the bottom of the dialog are "OK" and "Cancel" buttons.

These are the only changes you need to make. Leave the other settings on the defaults.

Appendix C: Configuring AnyNet On the AS400

The following instructions are provided by NetManage.

1. Type the following command at the AS400 command prompt:

CHGNETA ALWANYNET(*YES)

This value can only be changed when the AnyNet controller is varied off. Vary on the controller to make the change effective. You can check this attribute with the **DSPNETA** command, and page down to the bottom.

2. Type the following command at the AS400 command prompt:

**CRTCTLAPPC CTLD(controller name) LINKTYPE(*ANYNW)
RMTCPNAME(same as controller name)
RMTNETID(*NETATR)**


For **(controller name)**, any name can be used. Only create one AnyNet controller per 255 users. ***If multiple AnyNet controllers are created, unpredictable results may occur.***

For any further questions, see your AS400 System Administrator's *User's Guide*.


Appendix D: Configuring Client Access Express To Work With PC*MILER-AS400

1. Install Client Access Express on your mileage server PC by running the **setup.exe** that is in the Express folder on your Client Access Express CD.
2. Go to the AS400 Operations Navigator. For new installations, a Navigator prompt will ask if you want to add a connection. You will need to know the IP Address of your AS400 and the System Name if you want to configure your connection using the AS400 System name. You will have to make a table entry in the PC's Hosts File. For NT or Windows 2000, the file is **C:\winnt\system32\drivers\etc\hosts**. For 95/98, **c:\windows\hosts.sam**.

Here we are adding an AS400 called **S102BWAM**, you can also use the IP address of your AS400.




For existing installations of Client Access Express, go into the AS400 Operations Navigator and right mouse click on your AS400 connection. Choose Properties to make changes or Verify to verify a connection.



The Connection Properties Window is used for changing existing connections or changing the Restart Settings for new connections.

NOTE: Client Access Express has the ability to change passwords in the user profile. If you are prompted for a new password, you will be making a permanent change in that user profile.

3. **Password Considerations** - There are several areas to consider with a Client Access Express installation. Client Access Express offers three Password options. You can choose to have the PC logged on manually to the AS400, have Client Access Express use the Windows User Name and Password, or you can specify a user profile and have the password typed in as needed.




The default user ID is the User Profile that the mileage server PC will be signing on to. This user will need the authority to create and delete data queues in either the ALKWIN Library or your Innovative Work Library.

If you choose to use the Windows User and Password, you have to have the Windows User Name and Password match the user profile and Password that you will be using for your mileage server PC to sign onto the 400 with. The Windows User and password must exactly match those in the user profile you are using.


In the event of a power loss, the PC will not connect to the AS400 until someone manually types in the Windows password. To get a PC to restart without prompting for a password, you have to set the Windows Password to nothing. AS400 security does not allow a null password. So if you want the mileage server PC to reconnect automatically after a power outage, you cannot use the Windows Password option.

If you want to have an unattended restart, your only option with Client Access Express is to store the User Profile Name and Password in the mileage server's .ini file. At this time, the password is not encrypted, but it is stored as text.



For auto-restart, you will also have to make the above settings in the Connection Properties dialog. (For new connections, right mouse click on your connection in the AS400 Operation Navigator, and choose properties to get this screen.)

4. **Verify the connection.** If a connection cannot be made, contact IBM for assistance.



Appendix E: The Sleep Feature For PC Connection/ IPL Issues

The Sleep Feature has been added to correct an issue in which the PC Distance Server (srv32.exe) does not reliably reconnect to the AS400 after an IPL or power down.

To activate the Sleep Feature, you need to send a message to the PC mileage server (**SRV32.exe**).

Included in your ALKWIN Library is a CL program called "queue". For queue to work you must have **alkwin** in your library list. You may have to compile the queue if you do not have the program – use the command **WRKOBJPDM**, with 12 on QCLSRC and 14 on queue.

The syntax for queue is:

Queue<space>('SP60')

where 60 is the number of seconds that you want the mileage server to sleep for. (**NOTE:** Queue is case sensitive; the SP has to be in caps.)

To put the mileage server to sleep for a 3-hour period before an IPL, you would have to run this command (with ALKWIN in your library list):

Call alkwin/queue<space>('SP10800')

You will need to test the Sleep Feature. On your mileage server, set up your screen so you can watch the mileage server's Server Log (SRV32.exe).

To bring up the Server Log, click on the Bart's Windows pull-down menu, or press ALT-W and choose Display server Log.

From a green screen, run PC*MILER and run a route from 10001 to 90009 to make sure that it is working. Watch the PC*MILER-AS400 Server's server log. You should see those ZIP codes show up in a line that starts out "**input=...**" This test is to ensure that you are working with the correct mileage server, and that it is working properly.

Now exit the green screen PC*MILER and send a 60-second sleep command:

Call queue<space>('SP60') press <ENTER>.

Watch the server log to see that it catches the sleep message. Finally, the mileage server should wake up and reconnect with the mileage server.

Now go back to the green screen PC*MILER and send another mileage request to test that the re-established connection is working properly. If it is working now, you can use this feature before your ipl's or power downs.

You can use the Work with Job Schedule Entries (WRKJOBSCDE) command to set up an automatic process.

Be sure to put it to sleep for a long enough period of time. If Bart (srv32.exe) wakes up too early (before the AS400 is back up) it won't be able to connect. Be sure to leave enough time between sending the sleep command and starting the ipl or power down.

Appendix F: PCMSERVE.INI Settings

The **pcmserve.ini** file resides on the mileage PC in the **c:\windows** or the **c:\winnt** folder. Values specified in **pcmserve.ini** will be used unless they are otherwise specified in the mileage request packet. PC*MILER|Streets uses **pmwssrv.ini**, and has a few additional key values included at the bottom of the chart.

Valid values for default and option settings in the **pcmserve.ini** that can be changed by the user are described below.

Key	Valid Values (Defaults)	Description
[Defaults]		
CalcType	<u>Practical</u>	Not supported by PC*MILER AS400. If routing type is not specified the default route type of Practical will be used.
Units	<u>Miles</u> Kilometers	What unit of measure should distance be shown in.
ChangeDest	<u>TRUE</u> FALSE	When optimizing the route, should the trip's destination be optimized also.
Borders	<u>TRUE</u> FALSE	Should the engine try to keep routes within the United States (F), or can they cross and recross the borders at will (T).
HubMode	<u>TRUE</u> FALSE	Calculate the routes from the origin to each stop (T), not through each stop (F).
AlphaOrder	<u>TRUE</u> FALSE	List the states in the State Report in alphabetical order, or in the order driven.
FerryMiles	<u>TRUE</u> FALSE	Use ferry distances in mileage and cost calculations (T), or don't use (F).

[Options]

CustomRoute	TRUE <u>FALSE</u>	Should Custom routing be used.
HazRoute (for PC*MILER Hazmat add-on only)	<u>None</u> General Explosive Inhalant Radioactive Corrosive Flammable	The default hazardous routing type: disabled, general material, explosive, inhalant, radioactive, corrosive, or flammable.
Light Vehicle	TRUE <u>FALSE</u>	Set to TRUE (T) for light vehicle routing and restriction overrides; FALSE (F) = heavy vehicle routing and obey restrictions.
PartialCityMatch	TRUE <u>FALSE</u>	Require exact match on city name strings (T) or match on partial city names (F). Primarily used for long city names like "Naval Shipyard Portsmouth N0018, VA, Portsmouth".
UseUSPostCodes	<u>TRUE</u> FALSE	When set to TRUE, if a 5-digit postal code might be a U.S. or a Mexican code, the U.S. code will be used. See section 4.3 for all UseUSPostCodes and UseMexPostCodes setting combinations. Default = True
UseMexPostCodes	TRUE <u>FALSE</u>	When set to TRUE, if a 5-digit postal code might be a U.S. or a Mexican code, the Mexican code will be used. Default = False NOTE: If UseUSPostCodes and UseMexPostCodes are both FALSE, or are not in

the INI, the default U.S. code will be used. See section 4.3 for a list of all setting combinations.

PC*MILER|Streets-specific Key values for pmwssrv.ini:

[Options]

UseStreets	<u>TRUE</u> <u>FALSE</u>	Should street-level (T) or highway-only (F) routing be used when stops are city names or ZIP codes.
MatchRoadNameOnly	<u>TRUE</u> <u>FALSE</u>	Set to (T) to match address on road name only.

Appendix G: AS400.LOG Error Codes

To create a log file of all mileage server input and outputs, click on the mileage server's **File** menu>**AS400 Control** and choose **Log to file**. The file created is **c:\ALK Technologies\pcmiler30\as400\as400.log**. **AS400.log** displays requests and responses in the exact format as they are received and sent by the mileage server. It is recommended that logging only be used for diagnostic purposes, as the log files get quite large.

PC*MILER Error Codes:

Error Codes	Value	Message
PCMS_INVALIDPTR	101	Invalid pointer
PCMS_NOINIFILE	102	The INI file was not found
PCMS_LOADINIFILE	103	Could not load the INI file
PCMS_LOADGEOCODE	104	Could not load location database
PCMS_LOADNETWORK	105	Could not load the network database
PCMS_MAXTRIPS	106	Too many open trips (limit of 8)
PCMS_INVALIDTRIP	107	Invalid trip ID
PCMS_INVALIDSERVER	108	Invalid server ID
PCMS_BADROOTDIR	109	Could not find RootDir setting in INI file
PCMS_BADMETANETDIR	110	Invalid PCMNetDir setting
PCMS_NOLICENSE	111	License infraction: too many users, or licenses not found
PCMS_TRIPNOTREADY	112	The trip is not ready to calculate
PCMS_INVALIDPLACE	113	Invalid place name (city, state not found)
PCMS_ROUTINGERROR	114	Calculation failed: portions of trip are invalid
PCMS_OPTERROR	115	Optimization failed: portions of the trip are invalid
PCMS_OPTHUB	116	Cannot optimize a trip in HUB mode
PCMS_OPT2STOPS	117	Not enough stops to optimize the trip
PCMS_OPT3STOPS	118	Not enough stops to optimize without changing destination
PCMS_NOTENOUGHSTOPS	119	Not enough stops to calculate the trip
PCMS_BADNETDIR	120	Bad network directory
PCMS_LOADGRIDNET	121	Error loading gridded network
PCMS_BADOPTIONDIR	122	Bad option directory
PCMS_DISCONNECTEDNET	123	Disconnected network
PCMS_NOTRUCKSTOP	124	Truck inaccessible stop
PCMS_INVALIDREGIONID	125	Invalid region ID
PCMS_CLOSINGERROR	126	Server did not shut down properly

PCMS_NORTENGINE	127	Server could not properly initialize internal routing component
PCMS_NODATASERVER	128	Server could not properly initialize internal routing component

PC*MILER/Streets Error Codes:

Error Codes	Value	Message
PCMS_INVALIDPTR	101	Invalid pointer
PCMS_NOINIFILE	102	The INI file was not found
PCMS_LOADINIFILE	103	Could not load the INI file
PCMS_LOADGEOCODE	104	Could not load location database
PCMS_LOADNETWORK	105	Could not load the network database
PCMS_MAXTRIPS	106	Too many open trips (limit=8)
PCMS_INVALIDTRIP	107	Invalid trip ID
PCMS_INVALIDSERVER	108	Invalid server ID
PCMS_BADROOTDIR	109	Invalid RootDir setting in INI file
PCMS_BADMETANETDIR	110	Invalid MetaNetDir setting in INI file
PCMS_NOLICENSE	111	License infraction: too many users, or licenses not found
PCMS_TRIPNOTREADY	112	The trip is not ready to calculate
PCMS_INVALIDPLACE	113	Invalid place name (city, state not found)
PCMS_ROUTINGERROR	114	Calculation failed: portions of trip are invalid
PCMS_OPTERROR	115	Optimization failed: portions of the trip are invalid
PCMS_OPTHUB	116	Cannot optimize a trip in HUB mode
PCMS_OPT2STOPS	117	Not enough stops to optimize the trip
PCMS_OPT3STOPS	118	Not enough stops to optimize without changing destination
PCMS_NOTENOUGHSTOPS	119	Not enough stops to calculate the trip
PCMS_BADNETDIR	120	Bad network directory
PCMS_LOADGRIDNET	121	Error loading gridded network
PCMS_BADOPTIONDIR	122	Bad option directory
PCMS_DISCONNECTEDNET	123	Disconnected network
PCMS_NOTRUCKSTOP	124	Truck inaccessible stop
PCMS_INVALIDREGIONID	125	Invalid region ID
PCMS_CLOSINGERROR	126	Closing error

Appendix H: Technical Implications of PC*MILER | Tolls

To accommodate the extra space needed for requesting and receiving Tolls Cost data, the request and response packet layouts were increased in size and the size of the response data queues was increased as detailed below.

Third party or In-house transportation software must be modified to utilize PC*MILER-AS400 with the Tolls Cost component. PC*MILER-AS400 with the PC*MILER|Tolls add-on module cannot replace previous versions of PC*MILER-AS400 without programming changes. See Chapter 7, *Using PC*MILER|Tolls With Other Transportation Software*, for more information.

Notes For Existing PC*MILER-AS400 Users:

- A set of 10 new trip parameters has been inserted into all of the request and response packets.
- All return types (CP, SR, HR) were expanded to hold Tolls Cost information. CP was expanded by 7 characters, SR by 77, and HR by 63.

For PC*MILER|Tolls, the ROUTEINFO portion of the HS return was increased by seven characters and the number of ROUTEINFO sets per response packet was increased from three to nine to improve performance. For users who are upgrading from Version 15 or less, see NOTE below for previous changes.

- Output Data Queues sizes were lengthened from 1024 to 1048.
- Data Area "TLLALK" (renamed from COMALK) was modified to store a default setting for Tolls Cost requests.
- "Old mode" or short city names (22 characters) are not supported.


NOTE: In Version 16, the ROUTEINFO portion of the HS return was increased by 25 characters and the number of ROUTEINFO sets per response packet was decreased from four sets to three. Route Number was increased 15 characters from 20 to 35 (Highway, Road or Street Name), and Interchange City or Junction was increased 10 characters from 28 to 38.

The standard PC*MILER-AS400 distance server vs. the PC*MILER|Tolls-compatible version:

The mileage server executable name is "Srv32.exe". There are two distinct builds of this file: 1) the PC*MILER build and 2) the PC*MILER|Tolls build. If you have purchased the PC*MILER|Tolls add-on, both versions will be installed to C:\ALK Technologies\pcmiler30\AS400.

If the Tolls component is checked during installation, you will have the PC*MILER|Tolls build (Srv32.exe) and also “Srv32_Hwy.exe”, which is a renamed copy of the standard PCMILER build.


However, a different installation will occur if the Tolls component is unchecked during installation, or if you respond ‘Yes’ to this dialog:




In this case you will get a standard PC*MILER build named “Srv32.exe” along with “Srv32_Tolls.exe”, which is a renamed copy of the PC*MILER|Tolls build.

You can check to see which build you have by checking the file properties of your srv32.exe:

After installing with the Tolls component checked:



After installing without Tolls (Tolls component unchecked or answered 'Yes' to ICC user flag prompt):




The standard PC*MILER build for use with ALKWIN Library and existing third party applications is not modified to work with PC*MILER|Tolls, whereas the PC*MILER|Tolls build for use with ALKTLL Library and third party applications is written to work with the Tolls Cost component.

To Switch Between Versions After Installation:

Standard Highway to Tolls:

1. Stop the PC Mileage Server (srv32.exe)
2. Rename C:\ALK Technologies\pcmiler30\AS400\Srv32.exe to "Srv32_Hwy.exe".
3. Make a copy of the Srv32_Tolls.exe, rename this copy that you made to "Srv32.exe".
4. Launch the Mileage Server.

5. After starting the Mileage Server you need to change the Library for data queues as follows:
 - a. Click the File drop-down menu.
 - b. Choose "AS400 Control" then "Change Library/Data Queue".
 - c. Change the ALKWIN to "ALKTLL". (AS400 users will need ALKTLL in their library lists.)



Converting Tolls Cost Component to Standard Highway:

1. Stop the PC Mileage Server (srv32.exe)
2. Rename C:\ALK Technologies\pcmiler30\AS400\Srv32.exe to "Srv32_Tolls.exe".
3. Make a copy of the Srv32_Hwy.exe, rename this copy that you made to "Srv32.exe".
4. Launch the Mileage Server.
5. After starting the Mileage Server you need to change the Library for data queues as follows:
 - a. Click the File drop-down menu.
 - b. Choose "AS400 Control" then "Change Library/Data Queue".
 - c. Change the ALKTLL to "ALKWIN".

Running Both a Standard Highway and Tolls Cost Version:

For PC*MILER:

1. Make a copy c:\windows\pcmsrv32.dll and rename the copy to "pmwssrv.ini".
2. Make a copy of c:\windows\pcmsrv32.dll and rename the copy to "pmwssrv.dll". Edit c:\windows\pmwssrv.ini in notepad and set the Library=value from "ALKWIN" to "ALKTLL," or from "ALKTLL" to "ALKWIN". If your existing Library= value is an ICC library, you must change it to another library.
3. Create a shortcut to either Srv32_Hwy.exe or Srv32_Tolls.exe. Set the command line parameters to 2 2 2 or 2 2 1 as below.

C:\ALK Technologies\pcmiler30\as400\SRV32_hwy.exe
<space>1<space>2<space>2 for Client Access Express Connections

C:\ALK Technologies\pcmiler30\as400\SRV32_hwy.exe
<space>1<space>2<space>1 for NS Router Connections

For PC*MILER|Streets:

1. Edit c:\windows\pcmsrv32.dll in Notepad and set the Library=value from "ALKWIN" to "ALKTLL", or from "ALKTLL" to "ALKWIN". If your existing Library= value is an ICC library, you must change it to another library.
2. Create a short cut to either Srv32_Hwy.exe or Srv32_Tolls.exe
Set the command line parameters to 1 2 2 or 1 2 1 as below.

C:\ALK Technologies\pcmiler30\as400\ SRV32_HWY.exe
<space>2<space>2 <space>2 for Client Access Express Connections

C:\ALK Technologies\pcmiler30\as400\SRV32_HWY.exe
<space>2<space>2 <space>1 for NS Router Connections

Appendix I: Renamed Program Objects

PC*MILER-AS400 with the optional Tolls Cost component (PC*MILER|Tolls) is a modified version of the standard PC*MILER-AS400 version. The following objects have been renamed to avoid conflicts with existing PC*MILER products. **NOTE:** Some objects have been renamed twice to adhere to an updated naming policy.

ALKWIN library ⇒ ALKMVS ⇒ ALKMTL
ALKWIN/Miinqc ⇒ ALKMTL/TOLLINQ (RPG Mileage Inquiry Program)
ALKWIN/Miinqc ⇒ ALKMTL/TOLLINQC (CL program that creates a response data queue and then calls ALKMTL/MTLIINQ)
PCMILER Cmd ⇒ PCMTLL Cmd (Calls ALKTLL/ TOLLINQC)

External Data Structures

Used for sending and receiving trip information to/from data queues.

ALKWIN/MISEND ⇒ ALKTLL/NWSEND ⇒ ALKTLL/TLSEND
ALKWIN/MIRESP ⇒ ALKTLL/NWRESP ⇒ ALKTLL/TLRESP
ALKWIN/DRAW ⇒ ALKTLL/TLDRW
ALKWIN/MISEND2 ⇒ ALKTLL/TLSEND2 added for V22 to include specific field mappings from Borders Open/Closed and Use Ferry Distance flags. These data structures are not used by ALK at this time.

Print File

ALKWIN/MIINQPF ⇒ ALKTLL/TLINQPF

Stop (City) Validation

ALKWIN/CITALK ⇒ ALKTLL/CITTLL (RPG program that parses user input and calls VTLADR for PC side validation)
ALKWIN/VALADR ⇒ ALKTLL/VTLADR

Saved Routes (Turn by Turn Instructions) and Trips

ALKWIN/ROUTES ⇒ ALKTLL ⇒ RTESTL (Saved Directions)
ALKWIN/STOPS ⇒ ALKTLL/STPTL (Saved Trips)
ALKWIN/LOADST ⇒ ALKTLL/LOADTL (RPG Program Loads Saved Trips)
ALKWIN/SAVEST ⇒ ALKTLL/SAVETL (RPG Program Saves Trip)

Storage of Trip Parameters

ALKWIN/COMALK ⇒ ALKTLL/COMTLL (Data Area for storing startup Trip Parameters)
ALKWIN/Config ⇒ ALKTLL/TLLFIG (Program for setting Trip Parameters)

Display Files

ALKWIN/CONFIGD ⇒ ALKTLL/TLLFIGD
ALKWIN/MINQD ⇒ ALKTLL/TOLLINQD


ALKWIN/STOPSD ⇒ ALKTLL/STPTLD
ALKWIN/SAVESTD ⇒ ALKTLL/SAVETLD
ALWIN/VALHLPD ⇒ ALKTLL/VALHTLD

Appendix J: Setting Toll Discount Program Membership

Toll Discount membership is set on your PC Mileage Server. Changes are made within the desktop PC*MILER program (C:\ALK Technologies\pcmiler30\ App\ pcmwin32.exe).

On your Mileage Server PC:

1. Click Start → Programs → PCMILER 30 → PCMILER 30 (alk.pcmiler.exe).
2. Click File → Application Settings.
3. Click Tolls.
4. Check the appropriate boxes as pictured below.
5. Exit alk.pcmiler.exe.



After making changes to your Discount settings and exiting PC*MILER, you must shut down and restart your mileage server (srv32.exe):

Click Start → Programs → PCMILER 30 → AS400 Interface


The AS400 Interface (srv32.exe) only reads optional settings at Startup.

Appendix K: Setting the Default Cost Per Mile or Kilometer

For users who interpret the trip cost value as the trip distance in hundredths of miles or kilometers, the method for changing the default cost per mile or kilometer was changed in Version 24. If upgrading from v. 23 or older, follow the steps below.

Before starting the PC Distance Server (srv32.exe), first run the desktop program (alk.pcmiler.exe) and follow these steps:

1. Click the File menu → Application Settings to open the Application Settings dialog, then click the Route Costs



2. In the Route Costs Section, change the following values to **0**:
 - Greenhouse Gases
 - Fuel Cost Per Gallon
 - Miles per Gallon
 - Labor Cost Per Hour
3. Set Other Cost Per Mile Loaded and Empty to **1**.
4. Click **Save** to save the edits and close the dialog.
5. Exit the Desktop PC*MILER program, then start your PC Distance Server.

Appendix L: Running PC*MILER and PC*MILER|Tolls Builds of the AS400 Interface on the Same PC

These instructions are intended for use if you are required to run a Tolls build and a Non-Tolls build of the PC AS400 Interface (Srv32.exe, also known as 'Bart') on the same PC. Where noted, this method can also be used if you need to run two AS400 Interfaces connected to two different AS400s.

Background

With the purchase of the optional PC*MILER|Tolls module, you will have two separate builds of the PC AS400 Interface installed (Srv32.exe and Srv32_Tolls.exe or Srv32_Hwy.exe).

You will be making copies of two files used by the AS400 Interface, copying and editing your existing shortcut, and changing the Library= value in the appropriate INI file (Change System=, User=, and Pass= values for dual AS400 configurations).

There are two types of shortcut or command line properties available to start your PC AS400 Interface:

C:\ALK Technologies\pcmiler30\AS400\Srv32.exe 1 2 2

and

C:\ALK Technologies\pcmiler30\AS400\Srv32.exe 2 2 2

With **1 2 2**, srv32.exe will link to C:\windows\pcmsrv32.dll and pcmserve.ini while **2 2 2** will link to c:\windows\pmwssrv.dll and pmwssv.ini.

After installing, you will have one of these configurations as a starting point:

Case 1: PC*MILER Highway Only with PC*MILER Build of Bart - Parameters 1 2 2

Case 2: PC*MILER Highway Only with PC*MILER|Tolls Build of Bart - Parameters 1 2 2

Case 3: PC*MILER|Streets with PC*MILER Build of Bart - Parameters 2 2 2

Case 4: PC*MILER|Streets with PC*MILER|Tolls Build of Bart - Parameters 2 2 2

Case 5: Adding second Bart to service second AS400


Your Srv32.exe will either be a PC*MILER Build or a PC*MILER|Tolls Build, you must check Srv32.exe's file properties to determine the build that was installed.

See Steps 1 – 3 on the following pages.


Step 1: What is my configuration?

1. Start=> Programs=> PCMILER 30=> Right Click=> Bart=> Properties.
2. Read the 'Target' Parameters, will be 1 2 2 or 2 2 2.
3. Hit 'Open File Location' button, do a right mouse click=> properties on Srv32.exe.
4. In the 'General' tab will be either **PC*MILER Build** or **PC*MILER|Tolls Build**.


View of Interface properties:




Right-click Srv32.exe and select 'Properties':



After right-clicking properties on Srv32.exe, you will see either **PC*MILER Build**:



or **PC*MILER|Tolls Build**:



Step 2: Copy C:\Windows DLL and INI File

For parameters of **1 2 2** make a copy of c:\windows\pcmsrv.ini and rename this copy to pmwssrv.ini. Make a copy of c:\windows\pcmsrv32.dll and rename this copy to pmwssrv.dll.

For parameters of **2 2 2** compare the date and size of c:\windows\pmwssrv.dll to pcmsrv32.dll and compare the contents of pcmsrv32.dll to pcmsrv32.dll and compare the contents of pcmsrv32.dll to pcmsrv32.dll. If they do not match, rename pcmsrv32.dll and pcmsrv32.dll and then make a copy of pmwssrv.dll and rename the copy to pcmsrv32.dll. Make a copy of pmwssrv.ini and rename the copy pcmsrv32.dll. Make a copy of pmwssrv.ini and rename the copy pcmsrv32.dll.

Edit your new INI file:

For adding a Tolls or a Non-Tolls Bart you will be changing the Library= value from or to ALKWIN or ALKTLL or your custom library name.

For running a second Bart servicing a second AS400, change the System=, User=, and Pass= values to point to your second AS400, you will have to configure your Client Access Express to see your second AS400. You may have to change the Library= value as well.

Step 3: Create a New Shortcut

1. Right Click Start=> Open All Users or Click Start=> All Programs=> Right Click=> Open All Users.
2. Navigate to Programs=> PCMILER 30.
3. Right click=> copy Bart.
4. Right click=> paste Bart.
5. Right click=> properties new Shortcut.

For Case 1 (above, in the 'Background' section): PC*MILER Highway Only with PC*MILER Build of Bart, Parameters 1 2 2 – change the end of the target line from 'srv32.exe 1 2 2' to 'srv32_tolls.exe 2 2 2'.

For Case 2: PC*MILER Highway Only with PC*MILER|Tolls Build of Bart, Parameters 1 2 2 – change the end of the target line from 'srv32.exe 1 2 2' to 'srv32_hwy.exe 2 2 2'.

For Case 3: PC*MILER|Streets with PC*MILER Build of Bart, Parameters 2 2 2 – change the end of the target line from 'srv32.exe 2 2 2' to 'srv32_tolls.exe 1 2 2'.

For Case 4: PC*MILER|Streets with PC*MILER|Tolls Build of Bart, Parameters 2 2 2 – change the end of the target line from 'srv32.exe 2 2 2' to 'srv32_hwy.exe 1 2 2'.

For Case 5: Adding second Bart to service second AS400 – change the end of target line from '1 2 2' to '2 2 2' or from '2 2 2' to '1 2 2'.